Hello,

first of all could you please specify the preferable interface which you are intend to use inside VE (venet or veth)?

in case of venet:
- you should set appropriate sysctl parameters as described for example here:

http://wiki.openvz.org/Quick_installation#sysctl

- to add 83.147.250.101 use standard "vzctl set $VEID --ipadd $IP --save" syntax (don't bother about netmask. Because you have default gateway pointing to venet0 inside VE every packet that's going out of your VE first of all reaches HN and you should set appropriate route on the HN (may be pointing to 83.147.250.2 or may be you already have such route on the HN and in this case you haven't to do additional steps))