

---

Subject: Re: unable to open pty while entering - tried common solutions..

Posted by [lj2012](#) on Tue, 27 Jan 2009 15:52:41 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

sometimes udev is started from within rc.sysinit. Commenting out en making devices again works.

```
# vzctl exec 4444 vi /etc/rc.sysinit
```

(search for start\_udev and comment out)

```
# vzctl exec 4444 cat /etc/rc.sysinit | grep udev
##/sbin/start_udev
```

```
# vzctl exec 4444 bash
cd /dev
MAKEDEV pty
MAKEDEV tty
exit
```

```
# vzctl stop 4444
# vzctl start 4444
```