
Subject: Re: Network setup how to do it.
Posted by [michaelvv](#) on Thu, 20 Aug 2009 12:00:02 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi Maratrus...

Yes it's a requirement from the HOSTING company..

The Firm where i work has a customer who had severe DDOS and they are moving behind blacklotus.net..

They have this requirement and they do not support OPENVZ so we are pretty lost...

The box is a Proxmox server and yesterday we where so desperate that we had an offer 500\$ for a working setup , but no useful surgesions....

I have read the WIKI's and things seems to work i just have a big problem now....

When i try to connect from INTERNET to the CT i hit the HOST.

Do you have a solution to this ????

A little info...

/Michael

The Proxmox PVE is debian based ,i know you know ..
I give you 3 configurations files here :

/etc/network/interfaces [HOST]

```
auto lo
iface lo inet loopback
```

```
iface eth0 inet manual
```

```
auto vmbr0
iface vmbr0 inet static
    address 192.168.1.106
    netmask 255.255.255.0
    gateway 192.168.1.216
    bridge_ports eth0
    bridge_stp off
    bridge_fd 0
    up route add -host 192.168.1.146 dev vmbr0
```

```
up route add -host 192.168.1.166 dev vmbr0
```

```
/etc/rc.d/rc.local [VE 101]
```

```
ifconfig eth0 192.168.1.146/30  
ip route add 192.168.1.106 dev eth0  
ip route add 192.168.1.166 dev eth0  
ip route add 192.168.1.216 dev eth0  
route add default gateway 192.168.1.216
```
