Subject: Re: HN Dropping Packets Posted by Vasily Tarasov on Fri, 23 Jun 2006 05:46:05 GMT View Forum Message <> Reply to Message

The message "Out of socket memory" appears in the following cases:

- 1) (The number of orphaned sockets in VE) >= 1/4 * (numtcpsock.barrier)
- 2) (The number of orphaned sockets in VE) > (sysctl's net.ipv4.tcp_max_orphans)
- 3) More sophisticated "memory" condition.

You can use google to find out what are orphaned sockets and why they appear.

Then you can increase numtcpsock barrier and sysctl's net.ipv4.tcp_max_orphans, if you wish.

The number orphaned sockets in the system you can see in /proc/net/sockstat.

Hope this help!