
Subject: Re: Req: Anyone have a how-to or checklist for Asterisk inside VPS?

Posted by [curx](#) on Sat, 15 Jul 2006 15:54:15 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

e.g. asterisk in vps with debian stable aka. "sarge"

```
$ apt-get install asterisk
```

```
$ nano /etc/defaults/asterisk
```

change:

```
RUNASTERISK=no -> yes
```

```
AST_REALTIME=yes -> no (for realtime, you need
```

```
$ /etc/init.d/asterisk start
```

modify the config files for asterisk, and done!

if you need capi or/and zaptel/zaphfc:

* for capi: you need the /dev files on you hw-node and vps:

```
crw-rw---- 1 root dialout 68, 0 Jan 3 2006 /dev/capi20
crw-rw---- 1 root dialout 68, 1 Jan 3 2006 /dev/capi20.00
crw-rw---- 1 root dialout 68, 2 Jan 3 2006 /dev/capi20.01
crw-rw---- 1 root dialout 68, 3 Jan 3 2006 /dev/capi20.02
[...]
```

/* if the files doesn' exist use mknod for creating it*/

and in your vps config add for directly access:

```
DEVICES="c:68:0:rw, c:68:1:rw, c:68:2:rw"
```

* for zaptel/zaphfc:

```
crw-rw---- 1 root dialout 196, 0 Jan 4 2006 ctl
crw-rw---- 1 root dialout 196, 1 Jan 4 2006 1
crw-rw---- 1 root dialout 196, 2 Jan 4 2006 2
crw-rw---- 1 root dialout 196, 3 Jan 4 2006 3
crw-rw---- 1 root dialout 196, 4 Jan 4 2006 4
[...]
```

```
crw-rw---- 1 root dialout 196, 253 Jan 4 2006 timer
```

```
crw-rw---- 1 root dialout 196, 255 Jan 4 2006 pseudo
```

```
crw-rw---- 1 root dialout 196, 254 Jan 4 2006 channel
```

/* if the files doesn' exist use mknod for creating it*/

and in your vps config

```
DEVICES="c:196:0:rw, c:196:2:rw, c:196:1:rw, c:196:253:rw,c:196:254:rw,c:196:255:rw"
```

if need both (capi and zaphfc)

```
DEVICES="c:68:0:rw, c:68:1:rw, c:68:2:rw c:196:0:rw, c:196:2:rw, c:196:1:rw,  
c:196:253:rw,c:196:254:rw,c:196:255:rw"
```

Regards,
Thorsten
