

---

Subject: Re: Can't update my kernel

Posted by [Ales](#) on Thu, 16 Aug 2012 15:09:06 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hmm... you seem to have kernel-firmware and vzkernel-firmware installed at the same time, which is odd - if I remember correctly, these should be conflicting. I might be wrong since I haven't used regular and OpenVZ kernels at the same time for quite a while... What I usually do is to uninstall regular kernels on our OpenVZ servers altogether.

As a very quick fix (unless you really need regular kernels) I'd advise you to either stop updating them or uninstall them completely.

So, either set your yum configuration to exclude kernel\* or use 'yum update -x kernel\*'.

To uninstall them, use 'yum remove kernel\*'. Make sure your /boot/grub/grub.conf still points to your OpenVZ kernel (vzkernel) afterwards and that you still have vzkernel and vzkernel-firmware installed, of course.

---