
Subject: [PATCH] vzctl enter: Forward error messages from child process

Posted by [ldv](#) on Thu, 24 Aug 2006 22:39:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

vzctl: do_enter():

- In child, redirect stdout and stderr to pipe.
- In parent, read child's output from pipe even if enter failed.

Signed-off-by: Dmitry V. Levin <ldv@altlinux.org>

I need to obtain more information about vzctl enter failure.

For example, if dev/ptmx is not available inside container, vzctl enter just fails with short "enter failed" message.

This patch forwards error messages issued by child process, e.g.

```
# vzctl enter 1234
```

```
enter into VPS 1234 failed
```

```
Unable to open pty: No such file or directory
```

```
src/enter.c | 7 ++++++-
```

```
1 files changed, 6 insertions(+), 1 deletions(-)
```

```
diff --git a/src/enter.c b/src/enter.c
```

```
index 69cdd02..e0013df 100644
```

```
--- a/src/enter.c
```

```
+++ b/src/enter.c
```

```
@@ -231,6 +231,8 @@ int do_enter(vps_handler *h, env_id_t vei
```

```
    close(in[1]); close(out[0]); close(st[0]);
```

```
    /* list of skipped fds -1 the end mark */
```

```
    close_fds(1, in[0], out[1], st[1], h->vzfd, -1);
```

```
+ dup2(out[1], 1);
```

```
+ dup2(out[1], 2);
```

```
    if ((ret = vz_chroot(root)))
```

```
        goto err;
```

```
    ret = vz_env_create_ioctl(h, veid, VE_ENTER);
```

```
@@ -297,7 +299,10 @@ err:
```

```
    raw_on();
```

```
    e_loop(fileno(stdin), in[1], out[0], fileno(stdout));
```

```
    } else {
```

```
- fprintf(stdout, "enter failed\n");
```

```
+ fprintf(stdout, "enter into VPS %d failed\n", veid);
```

```
+ set_not_blk(out[0]);
```

```
+ while (stdredir(out[0], fileno(stdout)) == 0)
```

```
+ ;
```

```
    }
```

```
    while ((waitpid(pid, &status, 0)) == -1)
```

```
        if (errno != EINTR)
```

```
--
```

