
Subject: VLAN setup - confusion/help :(
Posted by [tgault](#) on Fri, 25 Aug 2006 04:20:17 GMT
[View Forum Message](#) <> [Reply to Message](#)

hi,

i'm trying to configure VLAN access to a host and it configures everything but i can't get out from the VE.

basically what i'm trying to do is have VE0 on one VLAN and each of the VEs on a different VLAN to separate them out. the steps i've done are:

- installed latest devel kernel
- modprobe 8021q
- modprobe vethdev

- vconfig add eth0 900
- brctl addbr vzbr900

- echo 1 > /proc/sys/net/ipv4/conf/eth0/forwarding
- echo 1 > /proc/sys/net/ipv4/conf/eth0/proxy_arp

- brctl addif vzbr900 eth0.900

- vzctl create 101 --ostemplate centos-4-x86_64-minimal --ipadd 210.18.55.132 --hostname vztest1
- vzctl set 101 --veth_add veth101.0,00:12:34:56:78:9A,eth0,00:12:34:56:78:9B --save

- brctl addif vzbr900 veth101.0

- vzctl start 101

- vzctl exec 101 "ifdown venet0:0"
- vzctl exec 101 "ifconfig eth0 210.18.55.132 netmask 255.255.255.0 up"

when i ping the gateway (or anything) from VE101 i get nothing

when i start VE101, i get:

```
Starting VPS ...
VPS is mounted
Adding IP address(es): 210.18.55.132
arp send: 172.18.55.132 is detected on another computer : 00:00:0c:07:ac:01
vps-net_add WARNING: arp send -c 1 -w 1 -D -e 210.18.55.132 eth0 FAILED
Setting CPU units: 1000
Set hostname: vztest1
Processing veth devices
VPS start in progress...
```

any thoughts or suggestions as to what i'm doing wrong ?????

many thx

scatha
