
Subject: [PATCH 2.6.18] ext3: errors behaviour fix
Posted by [vaverin](#) on Wed, 04 Oct 2006 07:50:31 GMT
[View Forum Message](#) <> [Reply to Message](#)

From: Dmitry Mishin <dim@openvz.org>

EXT3_ERRORS_CONTINUE should be taken from the superblock as default value for error behaviour.

Signed-off-by: Dmitry Mishin <dim@openvz.org>

Acked-by: Vasily Averin <vvs@sw.ru>

Acked-by: Kirill Korotaev <dev@openvz.org>

```
--- linux-2.6.18/fs/ext3/super.c.e3erop 2006-09-20 07:42:06.000000000 +0400
+++ linux-2.6.18/fs/ext3/super.c 2006-10-03 15:51:44.000000000 +0400
@@ -1466,6 +1466,8 @@ static int ext3_fill_super (struct super
    set_opt(sbi->s_mount_opt, ERRORS_PANIC);
    else if (le16_to_cpu(sbi->s_es->s_errors) == EXT3_ERRORS_RO)
        set_opt(sbi->s_mount_opt, ERRORS_RO);
+   else
+       set_opt(sbi->s_mount_opt, ERRORS_CONT);

    sbi->s_resuid = le16_to_cpu(es->s_def_resuid);
    sbi->s_resgid = le16_to_cpu(es->s_def_resgid);
```
