## Subject: Checkpoint bug

Posted by dagr on Thu, 07 Dec 2006 10:17:34 GMT

View Forum Message <> Reply to Message

Again i get strange results with checkpointing

2.6.9-023stab032 SMP - RHEL4 x86 - vzctl version 3.0.13

[dagr@ws-ca dagr]\$ sudo vzctl start 555 Starting VE ... VE is mounted Adding IP address(es): 10.0.0.55 Setting CPU units: 1000 Set hostname: 10.0.0.55 VE start in progress... [dagr@ws-ca dagr]\$ sudo vzctl chkpnt 555 --suspend Setting up checkpoint... suspend... get context... Checkpointing completed succesfully [dagr@ws-ca dagr]\$ sudo vzctl chkpnt 555 --dump --dumpfile ./img Setting up checkpoint... join context.. dump... Checkpointing completed succesfully [dagr@ws-ca dagr]\$ sudo vzctl status 555 VEID 555 exist mounted running [dagr@ws-ca dagr]\$ sudo vzctl chkpnt 555 --kill Killing... [dagr@ws-ca dagr]\$ sudo vzctl status 555 VEID 555 exist mounted down [dagr@ws-ca dagr]\$ sudo vzctl restore 555 --undump --dumpfile ./img Restoring VE ... Starting VE ... VE is mounted undump... Adding IP address(es): 10.0.0.55 Setting CPU units: 1000 get context... VE start in progress... Restoring completed succesfully [dagr@ws-ca dagr]\$ sudo vzctl enter 555 enter into VE 555 failed [dagr@ws-ca dagr]\$ sudo vzctl stop 555 Stopping VE ... Unable to stop VE: operation timed out

After this there is no way to stop VPS without rebooting HN. Also /etc/init.d/vz stop is not able to stop it and just continuosly tries , hanging the whole server, so only hard reset helps !! After reboot vps is ok to run, start,stop,enter , until next try to dump and restore - i checked , its "restore" section which make it hang.

Before that i tried to restore dump on another hn - an got this

Adding IP address(es): 10.0.0.55

Setting CPU units: 1000

Error: undump failed: No such file or directory

Restoring failed:
rst\_file: -2 20496
rst\_files: -2
make\_baby: -2
rst\_clone\_children
VE start failed
Stopping VE ...
VE was stopped

VE is unmounted

Same error if i do all on same hn , but dont kill after making dump , but resume and then stop . Also i noticed that after killing - it doesnt umounts VPS , tried also umount after killing - didnt help

At least tell me - if the any way top stop it without restarting the HN?