

---

Subject: Re: vzctl start id "VE start in progress", vzctl status"VEID exist mounted down&quo

Posted by [kir](#) on Tue, 30 Jan 2007 05:03:20 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Oh I see. There is an open bug about it already in our bugzilla.

[http://bugzilla.openvz.org/show\\_bug.cgi?id=436](http://bugzilla.openvz.org/show_bug.cgi?id=436)

Still, I want to resolve this by adding -z argument handling to upstart.

I have already asked about it (see

[http://bugzilla.openvz.org/show\\_bug.cgi?id=436#c6](http://bugzilla.openvz.org/show_bug.cgi?id=436#c6)), but got no reply so far. Perhaps you could ask, too.

Stephen Fletcher wrote:

> Issue was due to running Ubuntu 6.10 Edgy as the guest. I tried

> re-symlinking <mountdir>/bin/sh to bash instead of dash but this did not

> help. Perhaps is due to Edgy using upstart daemon instead on regular init.

>

> Soon as I tried Debian sarge as guest it worked fine.

>

>

> -----Original Message-----

> From: users-bounces@openvz.org [mailto:users-bounces@openvz.org] On Behalf

> Of Kirill Korotaev

> Sent: Tuesday, 23 January 2007 11:19 PM

> To: users@openvz.org

> Subject: Re: [Users] vzctl start id "VE start in progress", vzctl

> status"VEID exist mounted down", vzctl enter "VE is not running"

>

> Stephen,

>

> Is there anything in dmesg?

>

> Thanks,

> Kirill

>

>

>> vzctl version 3.0.14

>>

>> root@stephens:~# uname -a

>> Linux stephens 2.6.18-028test010 #2 PREEMPT Thu Jan 11 18:20:08 EST

>> 2007

>> i686 GNU/Linux

>> root@stephens:~# cat /proc/vz/\*

>> Version: 2.7

>> 0 b 016 \*.\*

>> 0 c 006 \*.\*

```

>> 0 0 77
>> Version: 2.5
>> Version: 2.2
>>
>> VEID user nice system uptime
>>
> idle
>
>> strv uptime used maxlat
>> totlat numsched
>> Version: 1.0
>> cat: /proc/vz/vzaquota: Is a directory
>> qid: path usage softlimit hardlimit time
>> expire
>> 777: /vz/private/777
>> 1k-blocks 198888 1048576 1153434 0
>> 0
>> inodes 11473 200000 220000 0
>> 0
>> root@stephens:~# lsmod | grep vz
>> vznetdev 16928 1
>> vzethdev 10764 0
>> vzdquota 41748 1 [permanent]
>> vzmon 41988 2 vznetdev,vzethdev
>> vzdev 3972 4 vznetdev,vzethdev,vzdquota,vzmon
>> ipv6 279776 15 vzmon
>>
>> root@stephens:~# vzctl start 777
>> Starting VE ...
>> VE is mounted
>> Adding IP address(es): 192.168.99.2
>> Setting CPU units: 1000
>> VE start in progress...
>> root@stephens:~# vzctl status
>> VE id is not given
>> root@stephens:~# vzctl status 777
>> VEID 777 exist mounted down
>> root@stephens:~# vzctl enter 777
>> VE is not running
>> root@stephens:~# vzctl restore 777
>> Restoring VE ...
>> Error: No checkpointing support, unable to open /proc/rst: No such
>> file or directory root@stephens:~# ifconfig venet0
>> venet0 Link encap:UNSPEC HWaddr
>> 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
>> UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1
>> RX packets:0 errors:0 dropped:0 overruns:0 frame:0
>> TX packets:0 errors:0 dropped:0 overruns:0 carrier:0

```

```
>> collisions:0 txqueuelen:0
>> RX bytes:0 (0.0 b) TX bytes:0 (0.0 b) root@stephens:~# ip
>> route
>> <ethernet0ip>/27 dev eth0 proto kernel scope link src <ethernet0ip>
>> default via <localgwip> dev eth0
>>
>> Help? :)
>>
```

---