

---

Subject: help vzmigrate

Posted by [cheitac](#) on Fri, 18 Nov 2011 08:16:44 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hi All

I'm trying to move my VPS to another host with "vzmigrate --online -r no -v xx.xx.xx.x1 100" but some errors shows.

here is debug.

Quote:vzmigrate -r no -v --online 10.10.10.11 100

Starting online migration of CT 100 to 10.10.10.11

OpenVZ is running...

  Loading /etc/vz/vz.conf and /etc/vz/conf/100.conf files

  Check IPs on destination node: 10.10.10.11

Preparing remote node

  Copying config file

100.conf

100% 1764

1.7KB/s 00:00

No changes in CT configuration, not saving

  Creating remote container root dir

  Creating remote container private dir

Initializing remote quota

  Quota init

vzquota : (warning) Quota file exists, it will be overwritten

  Turning remote quota on

Syncing private

Live migrating container...

  Suspending container

Setting up checkpoint...

  suspend...

  get context...

Checkpointing completed succesfully

  Dumping container

Setting up checkpoint...

  join context..

  dump...

Checkpointing completed succesfully

  Copying dumpfile

dump.100

100% 148MB

9.9MB/s 00:15

  Syncing private (2nd pass)

Syncing 2nd level quota

  Dumping 2nd level quota

  Copying 2nd level quota

quotadump.100

100% 21

0.0KB/s 00:00

Load 2nd level quota  
Undumping container  
Restoring container ...  
Starting container ...  
Container is mounted  
undump...  
vzquota : (warning) Quota is running for id 100 already  
Adding IP address(es): 10.10.10.11  
Setting CPU limit: 50  
Setting CPU units: 800  
Setting CPUs: 1  
Error: undump failedStopping container ...  
: Invalid argument  
Restoring failed:  
Error: iptables-restore exited with 2  
Error: Most probably some iptables modules are not loaded  
Error: rst\_restore\_net: -22  
Container start failed  
Container was stopped  
Container is unmounted  
Error: Failed to undump container  
Resuming...  
vzquota : (error) Quota is not running for id 100

on destination host shows errors.

Quote:dmesg output shows:

CT: 100: started  
CPT ERR: ffff810136770000,100 :iptables-restore exited with 2  
CPT ERR: ffff810136770000,100 :Most probably some iptables modules are not loaded  
CPT ERR: ffff810136770000,100 :rst\_restore\_net: -22  
CT: 100: stopped

CT: 100: started  
CPT ERR: ffff810165346000,100 :NLMERR: -22  
CPT ERR: ffff810165346000,100 :NLMERR: -22  
CPT ERR: ffff810165346000,100 :NLMERR: -22  
CPT ERR: ffff810165346000,100 :NLMERR: -22  
CPT ERR: ffff810165346000,100 :NLMERR: -22  
CPT ERR: ffff810165346000,100 :NLMERR: -22  
CPT ERR: ffff810165346000,100 :NLMERR: -22  
CPT ERR: ffff810165346000,100 :NLMERR: -22  
CPT ERR: ffff810165346000,100 :NLMERR: -22  
CPT ERR: ffff810165346000,100 :iptables-restore exited with 1  
CPT ERR: ffff810165346000,100 :Most probably some iptables modules are not loaded  
CPT ERR: ffff810165346000,100 :rst\_restore\_net: -22

CT: 100: stopped

/var/log/messages

Nov 18 12:05:06 host kernel: CT: 100: started

Nov 18 12:05:06 host kernel: CPT ERR: ffff810136770000,100 :iptables-restore exited with 2

Nov 18 12:05:06 host kernel: CPT ERR: ffff810136770000,100 :Most probably some iptables modules are not loaded

Nov 18 12:05:06 host kernel: CPT ERR: ffff810136770000,100 :rst\_restore\_net: -22

Nov 18 12:05:07 host kernel: CT: 100: stopped

Nov 17 23:05:07 host kernel: CT: 100: started

Nov 17 23:05:07 host kernel: CPT ERR: ffff810165346000,100 :NLMERR: -22

Nov 17 23:05:07 host last message repeated 8 times

Nov 17 23:05:07 host kernel: CPT ERR: ffff810165346000,100 :iptables-restore exited with 1

Nov 17 23:05:07 host kernel: CPT ERR: ffff810165346000,100 :Most probably some iptables modules are not loaded

Nov 17 23:05:07 host kernel: CPT ERR: ffff810165346000,100 :rst\_restore\_net: -22

Nov 17 23:05:08 host kernel: CT: 100: stopped

thanks!

---