
Subject: *BUG REPORTED* Cannot configure VRRPD inside a VE

Posted by [oviney](#) **on Fri, 11 May 2007 17:42:11 GMT**

[View Forum Message](#) <> [Reply to Message](#)

Hi All:

I have recently been testing VRRPD () on a RHEL4 update 4 VE and ran into the following error when trying to configure...

Error:

```
<snippet>
cant open raw socket. errno=97. (try to run it as root)
</snippet>
```

Here is the command that I ran:

```
<snippet>
vrrpd -i eth0 -p 25 -v 1 172.17.8.181
</snippet>
```

So at a first guess, it would appear that the VE doesn't have promiscuous access to the Ethernet device.

Any help would be much appreciated.

Subject: Re: Cannot configure VRRPD inside a VE

Posted by [Vasily Tarasov](#) **on Mon, 14 May 2007 08:42:57 GMT**

[View Forum Message](#) <> [Reply to Message](#)

Hello,

How do you use the network from your VE? I mean, do you have a veth device or venet or probably you utilize a real network card in VE using --netdev_add option?

Thank you.

Subject: Re: Cannot configure VRRPD inside a VE

Posted by [oviney](#) **on Mon, 14 May 2007 13:31:57 GMT**

[View Forum Message](#) <> [Reply to Message](#)

Hi:

Inside the VE we are using a real device using the following command:

```
vzctl set ${VPS_UID} --netif_add eth0 --hostname ${VPS_HOSTNAME} --save
```

Here is a view of the network config:

```
[root@caotta000807lvz-1 ~]# ifconfig
eth0    Link encap:Ethernet HWaddr 00:18:51:AA:3B:B0
        inet addr:172.17.8.185 Bcast:172.17.8.255 Mask:255.255.255.0
          UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
          RX packets:219407258 errors:0 dropped:0 overruns:0 frame:0
          TX packets:22664160 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:4058108292 (3.7 GiB) TX bytes:2943543110 (2.7 GiB)
```

```
lo     Link encap:Local Loopback
        inet addr:127.0.0.1 Mask:255.0.0.0
          UP LOOPBACK RUNNING MTU:16436 Metric:1
          RX packets:1404231735 errors:0 dropped:0 overruns:0 frame:0
          TX packets:1805380421 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:2380079327 (2.2 GiB) TX bytes:2334986944 (2.1 GiB)
```

Subject: Re: Cannot configure VRRPD inside a VE

Posted by [Vasily Tarasov](#) on Mon, 14 May 2007 13:42:40 GMT

[View Forum Message](#) <> [Reply to Message](#)

Can you please, strace vrrpd (http://wiki.openvz.org/Stracing_a_program) and send the output to us.

Thank you!

Subject: Re: Cannot configure VRRPD inside a VE

Posted by [Tellerdreher](#) on Mon, 04 Jun 2007 12:15:36 GMT

[View Forum Message](#) <> [Reply to Message](#)

I do not use vrrpd but keepalived and have the same problem. The process cannot open the socket to send the multicast VRRP keepalive messages:

Jun 4 14:10:21 keepalived1 Keepalived_vrrp: cant open raw socket. errno=97

[pid 32119] socket(PF_INET, SOCK_RAW, 0x70 /* IPPROTO_??? */) = -1 EAFNOSUPPORT
(Address family not supported by protocol)

I am using 2.6.18-8.1.3.el5.028stab033.1

PS: /etc/protocols: 0x70 == 112 == VRRP

PPS: I think here is the "problem" (net/socket.c):

```
int vz_security_proto_check(int family, int type, int protocol)
...
    switch (family) {
        case PF_UNSPEC:
        case PF_PACKET:
        case PF_NETLINK:
        case PF_UNIX:
            break;
        case PF_INET:
            switch (protocol) {
                case IPPROTO_IP:
                case IPPROTO_ICMP:
                case IPPROTO_TCP:
                case IPPROTO_UDP:
                case IPPROTO_RAW:
                    break;
                default:
                    return -EAFNOSUPPORT;
            }
            break;
    ...
}
```

Is this really only a security check (you can only open sockets with protocol == 0(ip), 1(icmp), 6(tcp), 17(udp), 255(??) inside a VE)? Shouldn't this be configurable (with a Capability or so?)?

Subject: Re: Cannot configure VRRPD inside a VE

Posted by [Vasily Tarasov](#) on Wed, 06 Jun 2007 15:24:18 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello, I consider such situation as a BUG, can you please report about it to bugzilla?

Thanks,
Vasily.

Subject: Re: Cannot configure VRRPD inside a VE

Posted by [Tellerdreher](#) on Thu, 07 Jun 2007 07:13:07 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

opened as http://bugzilla.openvz.org/show_bug.cgi?id=611

Thanks!
