
Subject: *SOLVED* Shorewall

Posted by [maximiliano](#) on Tue, 04 Sep 2007 19:10:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello,

I have a problem with OpenVZ and I need help please. I search in forum but I dont find the solution to my problem.

I installed OpenVZ and I have shorewall install in Hardware Node.

From hardware Node to VPS I can ping and connect with ssh without any problem.
But when I want to ping from a lan machine to VPS, I cant. Why??

My shorewall's configuration is:

Zone

====

#ZONE TYPE

fw firewall

net ipv4

openv ipv4

Interfaces

=====

#ZONE INTERFACE BROADCAST OPTIONS

net eth0 detect

openv venet0 192.168.10.255 routeback

Policy

=====

#SOURCE DEST POLICY LOG

fw net ACCEPT

net all DROP info

all all REJECT info

rules

=====

Ping/ACCEPT fw openv

Ping/ACCEPT net openv

ACCEPT fw openv tcp 22

In the message log I cant see nothing so I dont know what can it be...

Thnx,

Best Regards

Maximiliano

Subject: Re: Shorewall
Posted by [maximiliano](#) on Tue, 04 Sep 2007 19:18:50 GMT
[View Forum Message](#) <> [Reply to Message](#)

Ok sorry to post, I found solution:

RULES

=====

```
Ping/ACCEPT fw openv
Ping/ACCEPT net openv
ACCEPT fw openv tcp 22
```

```
Ping/ACCEPT openv fw <-- add
Ping/ACCEPT openv net <-- add
```

Thnx Everyone
Best Regards
Maximiliano

Subject: Re: Shorewall
Posted by [maximiliano](#) on Tue, 04 Sep 2007 19:23:46 GMT
[View Forum Message](#) <> [Reply to Message](#)

Sorry but didn't work.

This work to ping from VPS -> Hardware Node

But I cant ping lan machines!

Can anyone help me please?

Thnx

Subject: Re: Shorewall
Posted by [Vasily Tarasov](#) on Wed, 05 Sep 2007 03:21:14 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,

First of all, tell us, please, does without the shorewall everything works as you expect? It will narrow the area of investigation greatly

Thank you,
Vasily

Subject: Re: Shorewall
Posted by [maximiliano](#) on Wed, 05 Sep 2007 11:28:21 GMT
[View Forum Message](#) <> [Reply to Message](#)

Yes, This was my first OpenVZ's installation and I did not have any problem to this. Hardware Node is installed with CENTOS 4.5 and OpenVZ 2.6.9-023stab044.4-smp kernel. I could create one VPS with centos 4 Metadata template and this work good. My only problem is when I start shorewall in the hardware node, I lost connection between VPS and Networks Machines and vice versa.

I think that the problem must be in the shorewall configuration but I cant see nothing in syslog. I reed something about add "options ip_contrack ip_contrack_enable_ve0=1" in /etc/modprobe.conf but nothing happend.

I think that OpenVZ is an excelent option for Virtualization and with a little knowledge and desire can use that very well.

If some person could configure shorewall with OpenVZ in the hardware Node please post configuration (interfaces,zones,policy and rules).

Best Regards
Maximiliano NC.

Subject: Re: Shorewall
Posted by [maximiliano](#) on Wed, 05 Sep 2007 12:45:43 GMT
[View Forum Message](#) <> [Reply to Message](#)

Ok People I found the solution to my problem...

When I raised shorewall service I could note this -> IP Forwarding Disabled!

So, to enable that I go to -> /etc/shorewall/shorewall.conf

and change IP_FORWARDING=Off to On!

This Solve All my problems.

I hope that this solution Helps to other people.

Thnx!
Best Regards

Maximiliano N. C.
maximiliano.arg@gmail.com
