

---

Subject: Problem In Cpanel, Disk Quota Doesnt working

Posted by [ataomega](#) on Fri, 25 Jan 2008 09:50:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

hi all,

in whm , i see quota for all users is unlimited and disk space used is 0 mb!

how can i fix it? can anyone please help me?

thanks

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working

Posted by [rickb](#) on Fri, 25 Jan 2008 10:27:54 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

search feature || wiki -> [http://wiki.openvz.org/Cpanel\\_quotas](http://wiki.openvz.org/Cpanel_quotas)

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working

Posted by [Arbvps.com](#) on Fri, 25 Jan 2008 15:50:07 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

uname -a

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working

Posted by [powervps](#) on Wed, 30 Jan 2008 07:59:29 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

you need to change in the

`/etc/sysconfig/vz-scripts/xxx.conf`

xxx node nr

setup it to `QUOTAUGIDLIMIT="3000"`

that will fix the problems

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working  
Posted by [SoftDux](#) on Sat, 12 Apr 2008 04:02:41 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

powervps wrote on Wed, 30 January 2008 09:59  
you need to change in the

```
/etc/sysconfig/vz-scripts/xxx.conf
```

```
xxx node nr
```

```
setup it to QUOTAUGIDLIMIT="3000"
```

that will fix the problems

Can you please explain to me what exactly this does / means?

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working  
Posted by [curx](#) on Sat, 12 Apr 2008 10:19:45 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

it the same like:

```
# vzctl set <CTID> --quotaugidlimit num
```

man page of vzctl, "Disk quota parameters":

```
[...]
```

```
--quotaugidlimit num--quotaugidlimit num
```

sets maximum number of user/group IDs in a VE for which disk quota inside the VE will be accounted. If this value is set to 0, user and group quotas will not be accounted inside the VE.

Note that if you have previously set value of this parameter to 0, changing it while the VE is running will not take effect.

```
[...]
```

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working  
Posted by [SoftDux](#) on Sat, 12 Apr 2008 11:03:46 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

ok, so setting the --diskspace won't make a difference then?

I currently have a VE with 10GB space, but want to increase it to 15 GB, which didn't work, as can be seen here:

```
vzquota show 1001; vzctl exec 1001 df -H
vzquota : (warning) Quota is running, so data reported from quota file may not reflect current values
```

resource	usage	softlimit	hardlimit	grace
1k-blocks	3374996	15728640	16777216	
inodes	122722	600000	660000	
Filesystem	Size	Used	Avail	Use% Mounted on
simfs	8.9G	4.6G	3.6G	57% /

I used

```
vzctl set --diskspace 15G:16G 1001 --save
```

Reading through the man page again, <http://openvz.org/documentation/mans/vzctl.8> - I don't fully understand this statement

--quotaugidlimit num

sets maximum number of user/group IDs in a VE for which disk quota inside the VE will be accounted. If this value is set to 0, user and group quotas will not be accounted inside the VE. Note that if you have previously set value of this parameter to 0, changing it while the VE is running will not take effect

what gid is this that it's talking about?

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working

Posted by [SoftDux](#) on Sat, 12 Apr 2008 11:40:19 GMT

[View Forum Message](#) <> [Reply to Message](#)

I've tried increasing the quota, but got an error:

```
vzctl set 1001 --quotaugidlimit 15 --save
Setting quota ugidlimit: 15
```

Unable to apply new quota values: ugid quota not initialized  
Saved parameters for VE 1001

```
[root@gandalf ~]# vzctl exec 1001 df -H
Filesystem      Size  Used Avail Use% Mounted on
simfs           8.9G  4.6G  3.6G  57% /
```

What is the proper way of increasing the quota? I have searched the forum already, which is how I got to this thread, but didn't find an answer

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working  
Posted by [SoftDux](#) on Tue, 15 Apr 2008 13:14:50 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Can someone please help me? I urgently need to upgrade the space on a VPS for a client, but can't

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working  
Posted by [curx](#) on Tue, 15 Apr 2008 16:41:36 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

sorry for delay,  
there a two "quota systems" used by OpenVZ:

1 Level Quota:

-----

Space Hostnode to Container:

is set by --diskspace barrier:limit (/--diskinode barrier:limit)

config how much a container can use the diskspace/inodes on the hardware node

2Level Quota:

-----

is how many User/Group in this container can use the space above,

set by --quotauidlimit num (= limit of quota u(ser) g(roup)id) set how many User/Groups ID are accounted)

For setting User/Group Quota in your CT you can use the console quota tools, like edquota etc or use any config (panel) software.

> "you must restart your CT for taken any effects and ..."

restart your CT and you can use the 2level quota, but increase the number of quotauidlimit, it's to small!

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working  
Posted by [SoftDux](#) on Tue, 15 Apr 2008 19:39:44 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Thank you for that explanation, it wish it was in the wiki

so, if I have 100 accounts in cPanel, then 150 should be a good amount for the gidquota?

---

---

Subject: Re: Problem In Cpanel, Disk Quota Doesnt working  
Posted by [hostingbiniz](#) on Tue, 14 Jul 2009 12:46:25 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

OK here is the solution for VPS.  
Please try following it worked for me.

1- First change the /etc/fstab file similr to as follows:

```
# This file is edited by fstab-sync - see 'man fstab-sync' for details
LABEL=/ / ext3,usrquota defaults 1
LABEL=/boot /boot ext3 defaults 1 2
none /dev/pts devpts gid=5,mode=620 0 0
none /dev/shm tmpfs defaults 0 0
none /proc proc defaults 0 0
none /sys sysfs defaults 0 0
LABEL=SWAP-sda2 swap swap defaults 0 0
```

2- change in the

```
/etc/sysconfig/vz-scripts/xxx.conf
```

```
setup it to QUOTAUGIDLIMIT="3000"
reboot
```

3- this command as well as in sequence :

```
quotaoff -av
quotaon -av
/scripts/fixquotas
```

it should solve the issue

---