
Subject: *solved* cant login to virtual machine from other computers

Posted by [alex905](#) on Sun, 03 Feb 2008 17:56:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

i can log into my virtual machine from the host machine but not from remote computers. i can log into the host machine from remote computers though.

i added the ip 192.168.0.4 to the host machine at first (yes this is all on a private network) and then added the ip 192.168.0.5 to the virtual machine. a full restart later and no luck.

i then added the ip 192.168.0.5 as a second ip to the host machine by creating the file

```
ifcfg-eth0:1
```

the contents of the file are as follows

```
DEVICE=eth0
ONBOOT=yes
BOOTPROTO=static
IPADDR=192.168.0.5
NETMASK=255.255.255.0
GATEWAY=192.168.0.1
```

i noticed that the ifcfg-venet0 file on the host machine contains this code:

```
DEVICE=venet0
ONBOOT=yes
STARTMODE=onboot
```

is this normal or should this contain more information.

here is the output from the ifconfig command on the virtual machine.

```
lo      Link encap:Local Loopback
        inet addr:127.0.0.1  Mask:255.0.0.0
        UP LOOPBACK RUNNING  MTU:16436  Metric:1
        RX packets:4132306944 errors:0 dropped:0 overruns:0 frame:0
        TX packets:4096 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)

venet0  Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        -00
        inet addr:127.0.0.1  P-t-P:127.0.0.1  Bcast:0.0.0.0  Mask:255.255.255.
        255
        UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
        RX packets:102 errors:0 dropped:0 overruns:0 frame:0
        TX packets:71 errors:0 dropped:0 overruns:0 carrier:0
```

collisions:0 txqueuelen:0
RX bytes:8686 (8.4 KiB) TX bytes:8091 (7.9 KiB)

venet0:0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
-00
inet addr:192.168.0.6 P-t-P:192.168.0.6 Bcast:192.168.0.6 Mask:255.
255.255.255
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1

seems kins jumbeded if you ask me. this is where i think the error is.

to add the ip i used the command

```
vzctl set 102 --ipadd 192.168.0.5 --save
```

any help is always greatly apriated.

Subject: Re: cant login to virtual machine from other computers
Posted by [rickb](#) on Sun, 03 Feb 2008 18:19:24 GMT
[View Forum Message](#) <> [Reply to Message](#)

Is your HN using nat? If so, display your iptables config. naturally to reach 192.168.0/24 from the net, you would need it.

Rick

Subject: Re: cant login to virtual machine from other computers
Posted by [alex905](#) on Sun, 03 Feb 2008 18:25:55 GMT
[View Forum Message](#) <> [Reply to Message](#)

```
# Load additional iptables modules (nat helpers)
# Default: -none-
# Space separated list of nat helpers (e.g. 'ip_nat_ftp ip_nat_irc'), which
# are loaded after the firewall rules are applied. Options for the helpers are
# stored in /etc/modules.conf.
IPTABLES_MODULES=""
```

```
# Unload modules on restart and stop
# Value: yes|no, default: yes
# This option has to be 'yes' to get to a sane state for a firewall
# restart or stop. Only set to 'no' if there are problems unloading netfilter
# modules.
```

```
IPTABLES_MODULES_UNLOAD="yes"
```

```
# Save current firewall rules on stop.
```

```
# Value: yes|no, default: no
```

```
# Saves all firewall rules to /etc/sysconfig/iptables if firewall gets stopped
```

```
# (e.g. on system shutdown).
```

```
IPTABLES_SAVE_ON_STOP="no"
```

```
# Save current firewall rules on restart.
```

```
# Value: yes|no, default: no
```

```
# Saves all firewall rules to /etc/sysconfig/iptables if firewall gets
```

```
# restarted.
```

```
IPTABLES_SAVE_ON_RESTART="no"
```

```
# Save (and restore) rule and chain counter.
```

```
# Value: yes|no, default: no
```

```
# Save counters for rules and chains to /etc/sysconfig/iptables if
```

```
# 'service iptables save' is called or on stop or restart if SAVE_ON_STOP or
```

```
# SAVE_ON_RESTART is enabled.
```

```
IPTABLES_SAVE_COUNTER="no"
```

```
# Numeric status output
```

```
# Value: yes|no, default: yes
```

```
# Print IP addresses and port numbers in numeric format in the status output.
```

```
IPTABLES_STATUS_NUMERIC="yes"
```

i im prety sure its not using nat. but if it is im guessing its going to be shown on the host machine's (i take it that HN was a typo for HM)ifconfig. so here it is:

```
eth0    Link encap:Ethernet  HWaddr 00:18:F8:0B:2F:52
        inet addr:192.168.0.4  Bcast:192.168.0.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        RX packets:85674 errors:0 dropped:0 overruns:0 frame:0
        TX packets:141758 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:1000
        RX bytes:19927881 (19.0 MiB)  TX bytes:25754199 (24.5 MiB)
        Interrupt:20 Base address:0xcc00
```

```
eth0:1  Link encap:Ethernet  HWaddr 00:18:F8:0B:2F:52
        inet addr:192.168.0.5  Bcast:192.168.0.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Base address:0xcc00
```

```
lo      Link encap:Local Loopback
        inet addr:127.0.0.1  Mask:255.0.0.0
        UP LOOPBACK RUNNING  MTU:16436  Metric:1
```

RX packets:199 errors:0 dropped:0 overruns:0 frame:0
TX packets:199 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:21462 (20.9 KiB) TX bytes:21462 (20.9 KiB)

venet0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1
RX packets:94 errors:0 dropped:0 overruns:0 frame:0
TX packets:132 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:11127 (10.8 KiB) TX bytes:10582 (10.3 KiB)

as you can see i edited venet0 a bit if its wrong please say and i will revert it back.

Subject: Re: cant login to virtual machine from other computers
Posted by [rickb](#) on Sun, 03 Feb 2008 18:27:20 GMT
[View Forum Message](#) <> [Reply to Message](#)

probably you need to read the wiki or seek help from a linux admin familiar with nat.

#iptables -L -n -t nat

Subject: Re: cant login to virtual machine from other computers
Posted by [alex905](#) on Sun, 03 Feb 2008 19:14:56 GMT
[View Forum Message](#) <> [Reply to Message](#)

i went through the trouble shooting but found nothing. and the computer im trying to ssh with is also on the private network so im pretty sure nat wont come into it.

here is the output from that command

Chain PREROUTING (policy ACCEPT)
target prot opt source destination

Chain POSTROUTING (policy ACCEPT)
target prot opt source destination

Chain OUTPUT (policy ACCEPT)
target prot opt source destination

Subject: Re: cant login to virtual machine from other computers

Posted by [alex905](#) on Sun, 03 Feb 2008 23:28:51 GMT

[View Forum Message](#) <> [Reply to Message](#)

fixed it. i had to add a virtual interface for every ip asined to a VE.

for example:

on my foirst virtual machine i assined it the IP 192.168.0.6 by issuing the command

```
vzctl set 102 --ipadd 192.168.0.6 --save (this is for the beifit of beginners)
```

then i edited a network interface created by openVZ

my /etc/sysconfig/network-scripts/ifcfg-venet0 reads

```
NAME=""
BOOTPROTO=none
DEVICE=venet0
NETMASK=255.255.255.0
MTU=1500
BROADCAST=192.168.0.255
IPADDR=192.168.0.6
NETWORK=192.168.0.0
ONBOOT=yes
```

then

because i have more then one virtual machine i need more then one IP so i assined another IP to the secound machine using the command above obviously substituting some commands and values where nesecary. (it was asined 192.168.0.7)

then i has to create a virtual interface for the venet0 interface. to do this i created the file ifcfg-venet0:1

which can be done using this command:

```
vi /etc/sysconfig/network-scripts/ifcfg-venet0:0
```

then filled it with this data.

```
NAME=""
BOOTPROTO=none
DEVICE=venet0:1
NETMASK=255.255.255.0
MTU=1500
BROADCAST=192.168.0.255
ONPARENT=yes
IPADDR=192.168.0.7
NETWORK=192.168.0.0
```

ONBOOT=yes

if your new to this and as lost as i was i hope this mini tut helps you.

oh and im not a bad speller im just really fooking lazy.

Subject: Re: *solved* cant login to virtual machine from other computers

Posted by [maratrus](#) on Mon, 04 Feb 2008 07:23:51 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

Can I ask you a question?

- Is it possible to ping your VPS from remote computers?

Subject: Re: *solved* cant login to virtual machine from other computers

Posted by [alex905](#) on Mon, 04 Feb 2008 07:38:51 GMT

[View Forum Message](#) <> [Reply to Message](#)

yes. but i find that missleading. it is a start in tring to get them connected but seeing as i was sometimes pinging the host and not the VE i stoped doing that and relyed on SSH.

Subject: Re: *solved* cant login to virtual machine from other computers

Posted by [maratrus](#) on Mon, 04 Feb 2008 08:27:00 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

1) When you add an ip address to VE you should not to create the eth0 alias and assign to it the same ip address.

2) When you add an ip address to VE you should not to create the venet0 alias and assign to it the same ip address.

3) I think that 2) is the reason why you ping HN instead of VPS.

4) Please check sysctl parameters http://wiki.openvz.org/Quick_installation#sysctl

5) You can use "tcpdump" to determine the net behavior.