
Posted by [enpx](#) on Sat, 13 Dec 2008 15:01:58 GMT

[View Forum Message](#) <> [Reply to Message](#)

VE.

```
proc      /proc          proc  nosuid,noexec,gid=proc
  0 0
devpts    /dev/pts      devpts
nosuid,noexec,gid=tty,mode=620 0 0
```

sles:/ # df -h

```
simfs      8,5G 163M 6,6G 3% /
udev       1005M  0 1005M  0% /dev
```

sles:/ # ps aux

```
USER      PID %CPU %MEM  VSZ  RSS TTY   STAT START  TIME COMMAND
root      1 0.0 0.0  644  280 ?    Ss   17:11  0:00 init [3]
root     23926 0.0 0.0 14144  488 ?    Ss   17:11  0:00
vzctl: pts/0
root     23927 0.0 0.2  6632 2628 pts/0  Ss   17:11  0:00 -bash
root     24509 0.0 0.1  4896 1584 pts/0  R+   17:43  0:00 ps aux
```

```
# grep DISK /etc/vz/conf/106.conf
DISKSPACE="100000000:110000000"
DISKINODES="50000000:51000000"
```

Posted by [enpx](#) on Sun, 14 Dec 2008 10:59:30 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
[root@master ~]# vzctl set sles --diskspace unlimited:unlimited --save
Saved parameters for VE 106
[root@master ~]# vzctl set sles --diskinodes unlimited:unlimited --save
Saved parameters for VE 106
[root@master ~]# vzctl restart sles
Restarting VE
Stopping VE ...
VE was stopped
VE is unmounted
Starting VE ...
vzquota : (warning) block_hard_limit [99] < block_current_usage [182088]
vzquota : (warning) inode_hard_limit [99] < inode_current_usage [9495]
VE is mounted
Adding IP address(es): 10.0.0.106
Running VE script: /etc/vz/dists/scripts/suse-add_ip.sh
  ERROR: Can't write to file /etc/sysconfig/network//
bash: line 355: /etc/sysconfig/network//ifcfg-venet0: Disk quota exceeded
Setting CPU units: 27365
Configure meminfo: 308454
Set hostname: sles
Running VE script: /etc/vz/dists/scripts/suse-set_hostname.sh
/bin/cp: cannot create regular file `/etc/hosts.14331': Disk quota exceeded
  ERROR: Can't copy file /etc/hosts
VE start in progress...
[root@master ~]# df | grep sles
/dev/mapper/lvm-vz--sles
          33G  25G  6.6G  79% /lvm/sles
[root@master ~]# vzctl exec sles df -h
Filesystem      Size  Used Avail Use% Mounted on
simfs           8.5G  178M  6.6G   3% /
udev            1005M    0 1005M   0% /dev
```

Posted by [maratrus](#) on Mon, 15 Dec 2008 09:08:45 GMT

[View Forum Message](#) <> [Reply to Message](#)

Quote:

```
# vzctl set sles --diskspace unlimited:unlimited --save
```

```
# vzctl exec 106 ls -l /etc/mtab
```

```
# vzctl stop 106  
# vzquota drop 106  
# vzctl start 106
```

Posted by [enpx](#) on Mon, 15 Dec 2008 09:44:00 GMT
[View Forum Message](#) <> [Reply to Message](#)

Quote:

Quote:

```
# vzctl set sles --diskspace unlimited:unlimited --save
```

```
[root@master ~]# vzctl set 106 --diskspace unlimited:unlimited --save
Saved parameters for VE 106
[root@master ~]# vzctl set 106 --diskinodes unlimited:unlimited --save
Saved parameters for VE 106
[root@master ~]# grep DISK /etc/vz/conf/106.conf
DISKSPACE="9223372036854775807:9223372036854775807"
DISKINODES="9223372036854775807:9223372036854775807"
```

Quote:

```
[root@master ~]# vzctl exec 106 ls -l /etc/mtab
lrwxrwxrwx 1 root root 12 Dec 13 17:08 /etc/mtab -> /proc/mounts
```

Quote:

```
# vzctl exec 106 ls -l /etc/mtab
```

```
# vzctl stop 106
# vzquota drop 106
# vzctl start 106
```

```
[root@master ~]# vzctl stop 106
Stopping VE ...
VE was stopped
VE is unmounted
[root@master ~]# vzquota drop 106
[root@master ~]# vzctl start 106
Starting VE ...
Initializing quota ...
```

```
vzquota : (warning) block_hard_limit [99] < block_current_usage [25268904]
vzquota : (warning) inode_hard_limit [99] < inode_current_usage [203728]
vzquota : (warning) block_hard_limit [99] < block_current_usage [25268904]
vzquota : (warning) inode_hard_limit [99] < inode_current_usage [203728]
VE is mounted
Adding IP address(es): 10.0.0.106
Running VE script: /etc/vz/dists/scripts/suse-add_ip.sh
  ERROR: Can't write to file /etc/sysconfig/network//
bash: line 355: /etc/sysconfig/network//ifcfg-venet0: Disk quota exceeded
Setting CPU units: 27365
Configure meminfo: 308454
Set hostname: sles.it-s.donpac.ru
Running VE script: /etc/vz/dists/scripts/suse-set_hostname.sh
/bin/cp: cannot create regular file `/etc/hosts.22023': Disk quota exceeded
  ERROR: Can't copy file /etc/hosts
VE start in progress...
[root@master ~]# grep DISK /etc/vz/conf/106.conf
DISKSPACE="9223372036854775807:9223372036854775807"
DISKINODES="9223372036854775807:9223372036854775807"
```

```
Dec 15 12:36:07 master kernel: CT: 106: started
Dec 15 12:36:07 master kernel: VZ QUOTA: disk hardlimit reached for id=106
Dec 15 12:36:07 master kernel: VZ QUOTA: file hardlimit reached for id=106
Dec 15 12:36:07 master kernel: ioctl32(showconsole:21008): Unknown cmd fd(0)
cmd(80045432){00} arg(bff80be8) on /dev/null
```

```
[root@master ~]# tail -n 2 /etc/vz/conf/106.conf
LOG_LEVEL="10"
VERBOSE="10"
```

Posted by [maratrus](#) on Mon, 15 Dec 2008 10:02:57 GMT
[View Forum Message](#) <> [Reply to Message](#)

/var/vzquota/"

Posted by [enpx](#) on Mon, 15 Dec 2008 10:20:32 GMT

[View Forum Message](#) <> [Reply to Message](#)

Quote:

Quote:

QUOTA: ... hardlimit reached

Quote:

/var/vzquota/"

```
[root@master ~]# ls -l /var/lib/vzquota/quota.106
-rw----- 1 root root 191 Dec 15 13:17 /var/lib/vzquota/quota.106
[root@master ~]# vzquota drop 106
[root@master ~]# ls -l /var/lib/vzquota/quota.106
ls: /var/lib/vzquota/quota.106: No such file or directory
```

Posted by [maratrus](#) on Mon, 15 Dec 2008 11:02:49 GMT

[View Forum Message](#) <> [Reply to Message](#)

Posted by [enpx](#) on Mon, 15 Dec 2008 20:17:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

Quote:

Posted by [maratrus](#) on Tue, 16 Dec 2008 06:35:15 GMT

[View Forum Message](#) <> [Reply to Message](#)
