
Subject: Ubuntu Jaunty VE is hanging during boot
Posted by [JimL](#) on Wed, 08 Apr 2009 01:19:41 GMT
[View Forum Message](#) <> [Reply to Message](#)

I installed the Intrepid x86 template and it went well. I need to have the latest avr compiler and so I upgraded to jaunty. It went fine, however when the ve boots, it hangs. Here's what's running at the time

```
ps -ef
UID    PID  PPID  C  STIME TTY      TIME CMD
root    1    0  0  05:08 ?        00:00:00 init [2]
daemon  180   1  0  05:08 ?        00:00:00 /sbin/portmap
root    237   1  0  05:08 ?        00:00:00 /bin/sh /etc/init.d/rc 2
syslog  263   1  0  05:08 ?        00:00:00 /sbin/syslogd -u syslog
root    265  237  0  05:08 ?        00:00:00 /bin/sh /etc/rc2.d/S11klogd start
root    273   1  0  05:08 ?        00:00:00 /bin/dd bs 1 if /proc/kmsg of /var/run/klogd/kmsg
klog    274  265  0  05:08 ?        00:00:00 /sbin/klogd -P /var/run/klogd/kmsg
klog    275  274  0  05:08 ?        00:00:00 [klogd] <defunct>
root    276   0  0  05:09 ?        00:00:00 vzctl: pts/0
root    277  276  0  05:09 pts/0    00:00:00 -bash
root    291  277  0  05:09 pts/0    00:00:00 ps -ef
```

Any one have a clue as to what's happening? It eventually gets past this but then hangs at

```
UID    PID  PPID  C  STIME TTY      TIME CMD
root    1    0  0  05:08 ?        00:00:00 init [2]
daemon  180   1  0  05:08 ?        00:00:00 /sbin/portmap
syslog  263   1  0  05:08 ?        00:00:00 /sbin/syslogd -u syslog
root    273   1  0  05:08 ?        00:00:00 /bin/dd bs 1 if /proc/kmsg of /var/run/klogd/kmsg
root    276   0  0  05:09 ?        00:00:00 vzctl: pts/0
root    277  276  0  05:09 pts/0    00:00:00 -bash
108    301   1  0  05:13 ?        00:00:00 /bin/dbus-daemon --system
root    322   1  0  05:13 ?        00:00:00 /usr/sbin/sshd
root    350   1  0  05:13 ?        00:00:00 /usr/sbin/xinetd -pidfile /var/run/xinetd.pid -stayal
root    491   1  0  05:15 ?        00:00:00 sendmail: MTA: accepting connections
avahi   506   1  0  05:15 ?        00:00:00 avahi-daemon: running [avrdev.local]
avahi   507  506  0  05:15 ?        00:00:00 avahi-daemon: chroot helper
root    549   1  0  05:15 ?        00:00:00 /usr/sbin/cron
root    582  277  0  05:16 pts/0    00:00:00 ps -ef
```

It never brings up the network.

Thanks,
Jim.

Subject: Re: Ubuntu Jaunty VE is hanging during boot
Posted by [maratrus](#) on Wed, 08 Apr 2009 07:58:09 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hello Jim,

Quote:

Any one have a clue as to what's happening? It eventually gets past this but then hangs at

What does it mean hangs?

The provided output contains the following line:

Quote:

```
root    276    0 0 05:09 ?    00:00:00 vzctl: pts/0
```

So, as far as I understand you're able to enter that VE and invoke commands. So, VE is alive.

The line

Quote:

```
root    1      0 0 05:08 ?    00:00:00 init [2]
```

means that init in runlevel-2.

So, it worth checking if networking service should work at all in runlevel-2.

Subject: Re: Ubuntu Jaunty VE is hanging during boot
Posted by [JijoSevilla](#) on Wed, 29 Apr 2009 09:18:08 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,

JimL wrote on Wed, 08 April 2009 09:19| installed the Intrepid x86 template and it went well. I need to have the latest avr compiler and so I upgraded to jaunty. It went fine, however when the ve boots, it hangs. Here's what's running at the time

```
ps -ef
UID      PID  PPID  C  STIME TTY      TIME CMD
root     1    0  0 05:08 ?        00:00:00 init [2]
daemon  180   1  0 05:08 ?        00:00:00 /sbin/portmap
root    237   1  0 05:08 ?        00:00:00 /bin/sh /etc/init.d/rc 2
syslog  263   1  0 05:08 ?        00:00:00 /sbin/syslogd -u syslog
root    265  237  0 05:08 ?        00:00:00 /bin/sh /etc/rc2.d/S11klogd start
root    273   1  0 05:08 ?        00:00:00 /bin/dd bs 1 if /proc/kmsg of /var/run/klogd/kmsg
klog    274  265  0 05:08 ?        00:00:00 /sbin/klogd -P /var/run/klogd/kmsg
klog    275  274  0 05:08 ?        00:00:00 [klogd] <defunct>
root    276   0  0 05:09 ?        00:00:00 vzctl: pts/0
```

```
root    277  276  0 05:09 pts/0    00:00:00 -bash
root    291  277  0 05:09 pts/0    00:00:00 ps -ef
```

Any one have a clue as to what's happening? It eventually gets past this but then hangs at
The initial stall is because of klogd. You can disable this by running:

```
vzctl exec $VEID update-rc.d -f remove klogd
vzctl restart $VEID
```

Temporarily, you can also kill the dd and klogd processes.

JimL wrote on Wed, 08 April 2009 09:19lt never brings up the network.

This part I haven't figured out, though, and am currently in the process of trying to figure out how to get a Jaunty VE running. Like with you, I was fine until Intrepid, but upgrading to Jaunty prevents the network from running.

Subject: Re: Ubuntu Jaunty VE is hanging during boot
Posted by [JijoSevilla](#) on Wed, 29 Apr 2009 10:07:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

JimL wrote on Wed, 08 April 2009 09:19I installed the Intrepid x86 template and it went well. I need to have the latest avr compiler and so I upgraded to jaunty. It went fine, however when the ve boots, it hangs.

...

It never brings up the network.

We've found a workaround to this problem, and have posted our solution:

<http://www.fs3.ph/article/ubuntu-904-in-an-openvz-ve>. We hope this works for you, too.

Cheers!

Subject: Re: Ubuntu Jaunty VE is hanging during boot
Posted by [JimL](#) on Tue, 05 May 2009 11:45:27 GMT

[View Forum Message](#) <> [Reply to Message](#)

Thank you for the update, when I get some time, I'll give it a try.

Jim.

Subject: Re: Ubuntu Jaunty VE is hanging during boot
Posted by [ibcl](#) on Thu, 07 May 2009 16:28:44 GMT

[View Forum Message](#) <> [Reply to Message](#)

Thanks a lot for that hint (basically creating /var/run/network), works for me.

Regards Christoph
