
Subject: mount --bind Bug in OpenVZ?

Posted by [divB](#) on Wed, 22 Apr 2009 21:20:46 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

The following scenario without OpenVZ:

```
# mount /dev/sda1 /home
# mount --bind /home /dest1
# mount --bind /home /dest2
...
```

Now the content from /home is mapped to dest1 and dest2. Now I want to unmount these mapping but never ever the original mount to /home:

```
# umount /dest1
# umount /dest2
...
# ls /home
(there are files)
```

Well this is how should bind-mounts work. Now OpenVZ comes into play. In \$VEID.mount, I have the following command:

```
mount --bind /home /var/lib/vz/root/${VEID}/home
```

When the VE starts everything is fine. In the \$VEID.umount-Skript I have the following command:

```
umount /home /var/lib/vz/root/${VEID}/home
```

But now suddenly /home has been unmounted too on the host!! But this should never ever happen!

```
# ls /home
...
```

When I just ignore unmounting the bind-mounts it seems to work without problems but it seems to be not elegant to me.

I just don't understand it. Without the mount-Scripts everything works fine. But inside the mount/umount script, the original mount (/dev/sda1 to /home on VE0) is unmounted too.

And this is a fiasco: I have mounted /home into multiple VEs stopping one VE which has /home mounted removes /home from all other VEs!

Does anybody know something about this issue?

Regards,
divB

Subject: Re: mount --bind Bug in OpenVZ?
Posted by [maratrus](#) on Thu, 23 Apr 2009 06:53:59 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,

Quote:
umount /home /var/lib/vz/root/\${VEID}/home

This is a wrong syntax.
Invoking such command from HN tells your system to umount home. No wonder that /home is unmounted.

Don't put anything in umount script in such situation because /home directory will be properly unmounted from inside a VE when a VE is stopped.
Look at /proc/mounts output inside VE. The information about bind mount can be obtained from it, so you can umount this directory from inside the VE and init scripts actually do this.

Subject: Re: mount --bind Bug in OpenVZ?
Posted by [divB](#) on Thu, 23 Apr 2009 09:29:11 GMT
[View Forum Message](#) <> [Reply to Message](#)

CORRECTION!!! This was a copy & paste error. Sorry.

I certainly meant:

```
umount /var/lib/vz/root/${VEID}/home
```

Sorry.

Now it is really a bug, isn't it?

However, you say I should just leave the umount-scripts empty? It is unmounted automatically? Is this really the "right way"?

(I always try to avoid using things without cleanup code - it seems to me like using malloc without free or like creating a service with "start" but without "stop"...)