
Subject: Re: Handle ip from inside VE
Posted by [piavlo](#) on Mon, 22 Oct 2007 17:58:46 GMT
[View Forum Message](#) <> [Reply to Message](#)

http://en.wikipedia.org/wiki/Proxy_ARP

If it might help , this is my network configuration for bridge:

```
projsrv1 ~ # cat /etc/vz/vznet.conf
#!/bin/bash
```

```
EXTERNAL_SCRIPT="/etc/vz/bin/vzbridge.add"
projsrv1 ~ # cat /etc/vz/bin/vzbridge.add
#!/bin/bash
```

```
CONFIGFILE=/etc/vz/conf/$VEID.conf
. $CONFIGFILE
VZHOSTIF=`echo $NETIF |sed 's/^.*host_ifname=(.*)$.*$/1/g`
```

```
BRIDGED_VES_REGEXP='(101|102|103)'
echo "$VEID" | egrep -e "$BRIDGED_VES_REGEXP" > /dev/null
if [ "$?" == "0" ]; then
```

```
    if [ ! -n "$VZHOSTIF" ]; then
        echo "According to $CONFIGFILE VE$VEID has no veth interface configured."
        exit 1
    fi
```

```
    ifconfig veth${VEID}.0 0
    brctl addif br0 veth${VEID}.0
    exit $?
```

```
fi
```

```
exit 0
projsrv1 ~ #
The eth0 is enslaved to br0
```
