Subject: [SOLVED] Errors when resuming live-migration
Posted by divB on Sat, 09 May 2009 20:04:29 GMT
View Forum Message <> Reply to Message

Hi,

Now I stopped apache before live migration. Now I get these awful messages:

```
# vzmigrate2 --remove-area no --keep-dst --online -v 192.168.200.2 302
OPT:--remove-area
OPT:--keep-dst
OPT:--online
OPT:-v
OPT:192.168.200.2
Starting online migration of VE 302 on 192.168.200.2
OpenVZ is running...
    Loading /etc/vz/vz.conf and /etc/vz/conf/302.conf files
    Check IPs on destination node:
Preparing remote node
    Copying config file
302.conf                                                    100% 1838
1.8KB/s   00:00
Saved parameters for VE 302
    Creating remote VE root dir
    Creating remote VE private dir
    VZ disk quota disabled -- skipping quota migration
Syncing private
Live migrating VE
    Suspending VE
Setting up checkpoint...
       suspend...
       get context...
Checkpointing completed succesfully
    Dumping VE
Setting up checkpoint...
       join context..
       dump...
Checkpointing completed succesfully
    Copying dumpfile
dump.302                                                    100%
2132KB   2.1MB/s   00:00
    Syncing private (2nd pass)
    VZ disk quota disabled -- skipping quota migration
    Undumping VE
Restoring VE ...
Starting VE ...
VE is mounted
```

undump...
Setting CPU units: 1000
Configure meminfo: 65536
Configure veth devices: veth302.0
Stopping VE ...
Error: undump failed: File exists
Restoring failed:
Error: NLMERR: -17
Error: open_deleted: no suffix
Error: rst_file: -17 86696
Error: rst_files: -17
Error: make_baby: -17
Error: rst_clone_children
VE start failed
VE was stopped
VE is unmounted

Error: Failed to undump VE
Resuming...

Any idea what could be the problem here?

divB