Subject: Can't Enter VE
Posted by scooter on Fri, 07 Apr 2006 02:06:36 GMT
View Forum Message <> Reply to Message

Any ever had a problem when you try and do vzctl enter ID says enter failed?

I had a customer who it happened twice and says he did nothing out of the ordinary and i got it to happen to me today.

Restarting the VE doesn't help either.

I'll put my config below to see if that matters much.

I believe that should be 128 meg minimum and 256 meg burst.

Only thing i did was trying to check out this one mailserver setup program

http://www.qmailtoaster.com/info/EZ-QmailToaster-MailServer. txt

ONBOOT="yes"

# Primary parameters
NUMPROC="586:586"
AVNUMPROC="293:293"
NUMTCPSOCK="586:586"
NUMOTHERSOCK="586:586"
VMGUARPAGES="32768:2147483647"

# Secondary parameters
KMEMSIZE="24059084:26464992"
TCPSNDBUF="5619439:8019695"
TCPRCVBUF="5619439:8019695"
OTHERSOCKBUF="2809719:5209975"
DGRAMRCVBUF="2809719:2809719"

# Auxiliary parameters
LOCKEDPAGES="256:256"
SHMPAGES="117928:117928"
PHYSPAGES="0:2147483647"
NUMFILE="9376:9376"
NUMFLOCK="937:1030"
NUMPTY="58:58"
NUMSIGINFO="1024:1024"
DCACHESIZE="5243277:5400576"
NUMIPTENT="500:500"
DISKINODES="4704540:5174994"

QUOTATIME="0"
CPUUNITS="9256"
QUOTAUGIDLIMIT="40000"
OFFLINE_MANAGEMENT="yes"
NAMESERVER="ip's here"

DISKSPACE="5200000:5200000"

OOMGUARPAGES="2147483647:2147483647"
PRIVVMPAGES="128000:131072"

IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle ipt_TCPMSS ipt_tcpmss ipt_ttl ipt_length"

Subject: Re: Can't Enter VE
Posted by dim on Fri, 07 Apr 2006 08:31:46 GMT
View Forum Message <> Reply to Message

Could you provide `cat /proc/user_beancounters` output relative to this VE?
Did you check /var/log/messages (it probably contains something weird)?

Subject: Re: Can't Enter VE
Posted by scooter on Fri, 07 Apr 2006 15:17:45 GMT
View Forum Message <> Reply to Message

well i can't enter it to give you a proc/user_beancounters unfortunately

And no i didn't think to check the var/log/messages unfortunately, before killing it. heh

But I'll do it again tonight and give it a shot.

Subject: Re: Can't Enter VE
Posted by dim on Fri, 07 Apr 2006 15:40:48 GMT
View Forum Message <> Reply to Message

I mean output on the hardware node.

Subject: Re: Can't Enter VE
Posted by kir on Sat, 08 Apr 2006 00:02:22 GMT

View Forum Message <> Reply to Message

Can you check if doing
vzctl exec NNN mount devpts /dev/pts -t devpts
before vzctl enter helps?

Subject: Re: Can't Enter VE
Posted by heymister on Thu, 20 Apr 2006 12:39:54 GMT
View Forum Message <> Reply to Message

I had the same problem with 2.6.16-1.2080_FC5.026test007 as node and gentoo-20060317-i686-stage3 as VE;

your suggestion did the trick
Bye
M