Subject: USB passthrough
Posted by deranjer on Tue, 04 Jan 2011 02:32:10 GMT
View Forum Message <> Reply to Message

How do I passthrough a usb HDD (ntfs) to a container?
I manage to get it to show up in the container under fdisk using the following command:

#vzctl set 1000 --devnode /dev/sdc1:rw --save

However, I can't mount it:

#ntfsmount /dev/sdc1 /mnt/Media -o force
fuse: failed to open /dev/fuse: Operation not permitted
fuse_mount failed.
Unmounting /dev/sdc1 (Media)

#modprobe fuse
WARNING: All config files need .conf: /etc/modprobe.d/00local, it will be ignored in a future release.
FATAL: Could not load /lib/modules/2.6.32-4-pve/modules.dep: No such file or directory

#ls /lib/modules
2.6.26-2-686 2.6.32-3-686

If I copy (I know.. it won't work lol.. I was trying anything) it...
#cp -r 2.6.32-3-686 2.6.32-4-pve

#modprobe fuse
FATAL: Error inserting fuse (/lib/modules/2.6.32-4-pve/kernel/fs/fuse/fuse.ko): Invalid module format

How do I get USB passthrough working?

Subject: Re: USB passthrough
Posted by mike on Sat, 16 Apr 2011 17:33:05 GMT
View Forum Message <> Reply to Message

1) it's not related to USB
2) it's related to FUSE
3) I've done FUSE under OpenVZ containing LTSP like this:

HN: load kernel module, configure passthrough
echo fuse >> /etc/modules
modprobe fuse

vzctl set 123 --devnodes fuse:rw --save

VE: check permissions
ls -l /dev/fuse /usr/bin/fusermount