Subject: *SOLVED* veth
Posted by youp on Sat, 23 Sep 2006 19:33:41 GMT
View Forum Message <> Reply to Message

i try to use veth
i use kernel 2.6.16-026test017 with FC4
i use config from http://wiki.openvz.org/Virtual_Ethernet_device

all work fine , but no broadcast in VPS

i check with : tcpdump -i eth0 port 137, nothing

here the command use

VE0 :

modprobe vzethdev

vzctl set 204 --veth_add veth204.0,10:12:34:56:78:9A,eth0,10:12:34:56:78:9B --save
vzctl start 204
vzctl exec 204 '/sbin/ifconfig eth0 0'
vzctl exec 204 '/sbin/ip addr add 192.168.1.9/24 dev eth0 broadcast 192.168.1.255'
vzctl exec 204 '/sbin/ip route del default dev venet0'
vzctl exec 204 '/sbin/ip route add default dev eth0'
ip route add 192.168.1.9 dev veth204.0
ifconfig veth204.0 0
echo 1 > /proc/sys/net/ipv4/conf/veth204.0/forwarding
echo 1 > /proc/sys/net/ipv4/conf/veth204.0/proxy_arp
echo 1 > /proc/sys/net/ipv4/conf/eth0/forwarding
echo 1 > /proc/sys/net/ipv4/conf/eth0/proxy_arp
ip route add 192.168.1.9 dev veth204.0 scope link src 192.168.1.5

can you help me ?
i would like to use samba into vps

Subject: Re: veth
Posted by Andrey Mirkin on Mon, 25 Sep 2006 10:52:13 GMT
View Forum Message <> Reply to Message

You have to create bridge on host node and add eth0 and veth device in it. After that samba should work fine.

Subject: Re: veth
Posted by szocske on Mon, 25 Sep 2006 11:00:40 GMT

I also have to do ifconfig vethVEID.0 up on the host (HW node).