Subject: vzmigrate error
Posted by Darryl Ross on Sat, 02 Dec 2006 01:18:57 GMT
View Forum Message <> Reply to Message

Hi All,

I'm having a problem migrating a guest from one machine to another. It's stopping with an error about the second level quotas, which I'm not using.

Is there a way to disable that?

Regards
Darryl

```
[root@noddy vz]# vzmigrate --keep-dst --online -r yes -v 172.16.1.225 241
OPT:--keep-dst
OPT:--online
OPT:-r
OPT:-v
OPT:172.16.1.225
Starting online migration of VE 241 on 172.16.1.225
OpenVZ is running...
   Loading /etc/vz/vz.conf and /etc/vz/conf/241.conf files
   Check IPs on destination node: 172.16.1.241
Preparing remote node
   Copying config file
241.conf
                                              100% 1816
  1.8KB/s   00:00
WARNING: Settings were not saved and will be resetted to original values
on next start (use --save flag)
   Creating remote VE root dir
   Creating remote VE private dir
Initializing remote quota
   Quota init
   Turning remote quota on
Syncing private
Live migrating VE
   Suspending VE
Setting up checkpoint...
      suspend...
      get context...
Checkpointing completed succesfully
   Dumping VE
Setting up checkpoint...
      join context..
      dump...
```

Checkpointing completed succesfully
Copying dumpfile
dump.241
100% 5212KB
5.1MB/s 00:00
Syncing private (2nd pass)
Syncing 2nd level quota
Dumping 2nd level quota
vzquota : (error) Can't open quota file for id 241, maybe you need to
reinitialize quota: No such file or directory
Failed to dump 2nd level quota
Resuming...
vzquota : (error) Quota is not running for id 241

Subject: Re: vzmigrate error
Posted by Vasily Tarasov on Mon, 04 Dec 2006 08:58:26 GMT
View Forum Message <> Reply to Message

This is easy to disable 2nd level quota: just remove line with
QUTAUGIDLIMIT for /etc/vz.conf and /etc/conf/<veid>.conf and restart VE.
You should do it on both nodes: source and destination.

HTH,
Vasily.

Darryl Ross wrote:
> Hi All,
>
> I'm having a problem migrating a guest from one machine to another. It's
> stopping with an error about the second level quotas, which I'm not using.
>
> Is there a way to disable that?
>
> Regards
> Darryl
