Subject: Bandwidth limiting crashes the machine Posted by eugeniopacheco on Wed, 03 May 2006 20:43:32 GMT

View Forum Message <> Reply to Message

Hi,

I'm running openvz on a Celeron 3066 with 1GB RAM and 160GB of disk space and I wished to limit traffic speed of a VPS. I searched the web and I came to a very interesting website: http://lartc.org/howto/

They offer a script (the script can be found at

http://lartc.org/howto/lartc.cookbook.ultimate-tc.html#AEN22 33 and I also added it later on) that limits download and upload speed by using htb. The problem is that when I use this script on the host, after some time (a day or two) the server crashes. I don't know if it's only the network connection that stops, or the entire machine freezes (it's a remote server), but I do know that the computer just stops answering. Can someone help me?

```
#!/bin/bash
# The Ultimate Setup For Your Internet Connection At Home
#
#
# Set the following values to somewhat less than your actual download
# and uplink speed. In kilobits
DOWNLINK=1024
UPLINK=1024
DEV=eth0
# clean existing down- and uplink gdiscs, hide errors
tc adisc del dev $DEV root 2> /dev/null > /dev/null
tc gdisc del dev $DEV ingress 2> /dev/null > /dev/null
##### uplink
# install root CBQ
tc gdisc add dev $DEV root handle 1: cbg avpkt 1000 bandwidth 10mbit
# shape everything at $UPLINK speed - this prevents huge queues in your
# DSL modem which destroy latency:
# main class
tc class add dev $DEV parent 1: classid 1:1 cbq rate ${UPLINK}kbit \
allot 1500 prio 5 bounded isolated
# high prio class 1:10:
```

```
tc class add dev $DEV parent 1:1 classid 1:10 cbq rate ${UPLINK}kbit \
 allot 1600 prio 1 avpkt 1000
# bulk and default class 1:20 - gets slightly less traffic,
# and a lower priority:
tc class add dev $DEV parent 1:1 classid 1:20 cbg rate $[9*$UPLINK/10]kbit \
 allot 1600 prio 2 avpkt 1000
# both get Stochastic Fairness:
tc qdisc add dev $DEV parent 1:10 handle 10: sfq perturb 10
tc gdisc add dev $DEV parent 1:20 handle 20: sfg perturb 10
# start filters
# TOS Minimum Delay (ssh, NOT scp) in 1:10:
tc filter add dev $DEV parent 1:0 protocol ip prio 10 u32 \
   match ip tos 0x10 0xff flowid 1:10
# ICMP (ip protocol 1) in the interactive class 1:10 so we
# can do measurements & impress our friends:
tc filter add dev $DEV parent 1:0 protocol ip prio 11 u32 \
match ip protocol 1 0xff flowid 1:10
# To speed up downloads while an upload is going on, put ACK packets in
# the interactive class:
tc filter add dev $DEV parent 1: protocol ip prio 12 u32 \
 match ip protocol 6 0xff \
 match u8 0x05 0x0f at 0 \
 match u16 0x0000 0xffc0 at 2 \
 match u8 0x10 0xff at 33 \
 flowid 1:10
# rest is 'non-interactive' ie 'bulk' and ends up in 1:20
tc filter add dev $DEV parent 1: protocol ip prio 13 u32 \
 match ip dst 0.0.0.0/0 flowid 1:20
# slow downloads down to somewhat less than the real speed to prevent
# queuing at our ISP. Tune to see how high you can set it.
# ISPs tend to have *huge* queues to make sure big downloads are fast
# attach ingress policer:
tc qdisc add dev $DEV handle ffff: ingress
# filter *everything* to it (0.0.0.0/0), drop everything that's
```

coming in too fast:

tc filter add dev \$DEV parent ffff: protocol ip prio 50 u32 match ip src \ 0.0.0.0/0 police rate \${DOWNLINK}kbit burst 10k drop flowid :1

Subject: Re: Bandwidth limiting crashes the machine Posted by Vasily Tarasov on Thu, 04 May 2006 08:17:03 GMT View Forum Message <> Reply to Message

Can you, please, specify what openVZ kernel version do you use? Thanks.

Subject: Re: Bandwidth limiting crashes the machine Posted by eugeniopacheco on Thu, 04 May 2006 09:48:55 GMT View Forum Message <> Reply to Message

I'm very sorry about that, I completely forgot the kernel, here goes all information on the machine:

```
[root@t248 ~]# uname -a
```

Linux t248.1paket.com 2.6.8-022stab072.2 #1 Mon Mar 20 14:19:14 MSK 2006 i686 i686 i386 GNU/Linux

[root@t248 ~]# vzlist

VPSID NPROC STATUS IP_ADDR HOSTNAME
101 73 running x.x.x.x x
102 66 running x.x.x.x x
103 23 running x.x.x.x x

[root@t248 ~]# vzmemcheck

Output values in %

LowMem LowMem RAM MemSwap MemSwap Alloc Alloc util commit util commit util commit limit

1.57 28.58 15.31 15.31 28.04 81.91 28.04 194.86

[root@t248 ~]# vzmemcheck -A

Output values in Mbytes

LowMem LowMem RAM MemSwap MemSwap Alloc Alloc util commit util commit util commit limit

5.12 93.45 153.22 153.22 280.68 819.98 280.68 1950.67

326.00 326.00 1001.00 1001.00 1001.00 1001.00 1001.00

[root@t248 ~]# vzmemcheck -Av

Output values in Mbytes

veid LowMem LowMem RAM MemSwap MemSwap Alloc Alloc util commit util util commit util commit limit

2.86 34.33 57.65 57.65 96.74 187.33 96.74 659.33

102 1.18 24.79 58.94 58.94 87.20 495.98 87.20 845.11

Summary: 5.12 93.45 153.22 153.22 280.68 819.98 280.68 1950.67

326.00 326.00 1001.00 1001.00 1001.00 1001.00 1001.00

[root@t248 ~]# vzcpucheck Current CPU utilization: 42664 Power of the node: 151267 [root@t248 ~]# cat /proc/cpuinfo

processor : 0

vendor id : GenuineIntel

cpu family : 15 model : 4

model name : Intel(R) Celeron(R) CPU 3.06GHz

stepping : 1

cpu MHz : 3061.389 cache size : 256 KB

fdiv_bug : no
hlt_bug : no
f00f_bug : no
coma_bug : no
fpu : yes
fpu_exception : yes
cpuid level : 5
wp : yes

flags : fpu vme de pse tsc msr pae mce cx8 apic sep mtrr pge mca cmov pat pse36 clflush dts acpi mmx fxsr sse sse2 ss ht tm pbe pni monitor ds cpl cid

bogomips : 6045.69

Also, if someone could please let me know where the virtual memory comes from I would much appreciate, for when I run vzmemcheck -Av it shows limit numbers at the bottom, and it shows that the limit on my server for alloc util is 1001, same as RAM, but the RAM is way underused, so the question is, can I use more alloc memory than 1001 or it is limited as the RAM is?

Thanks for all your help.

Regards,

Eugenio Pacheco

Subject: Re: Bandwidth limiting crashes the machine Posted by Vasily Tarasov on Fri, 05 May 2006 10:14:46 GMT

View Forum Message <> Reply to Message

Some comments.

In the script applied you use interface eth0, so you run it on the host machine. Then traffic control

affects all VPSs. Do you realy wish such effect? Inside VPS you can use interface venet0, to control traffic of this VPS only. But, of course, in this case, VPS root can change traffic control...

As concerns node crash. It's really necessary to know symptoms more precisely, /var/log/messages, etc. We even don't know was it crash or some network problem...

> Also, if someone could please let me know where the virtual memory comes from I would much appreciate, for when I run vzmemcheck -Av it shows limit numbers at the bottom, and it shows that the limit on my server for alloc util is 1001, same as RAM, but the RAM is way underused, so the question is, can I use more alloc memory than 1001 or it is limited as the RAM is?

vzmemcheck is rather strange utility on my mind =)

Bottom string is not limits actualy, it's just a real lowmem, totalmem and swap values of your node (with some coeff.)

I suggest you to use /proc/user_beancounters file, there you can see limits, barriers, helds in real units. Also "OpenVZ User's Guide" contains information about this file.

Thanks.

Subject: Re: Bandwidth limiting crashes the machine Posted by eugeniopacheco on Sat, 06 May 2006 10:22:17 GMT

View Forum Message <> Reply to Message

Hi,

Thanks a lot for all the answers, it really helped me.

Right after I posted this problem with bandwidth limit, I also thought of using the device venet0, but it only limited the incoming bandwidth, not the outgoing, so I had the idea of making another script and it's running 3 days ago with no problems (at least up to now) Here it goes:

#!/bin/bash

DEV=eth0

tc qdisc del dev \$DEV root

tc qdisc add dev \$DEV root handle 1: cbq avpkt 1000 bandwidth 100mbit

tc class add dev \$DEV parent 1: classid 1:1 cbq rate 1024kbit allot 1500 prio 5 bounded isolated

tc filter add dev \$DEV parent 1: protocol ip prio 16 u32 match ip src x.x.x.x flowid 1:1

tc qdisc add dev \$DEV parent 1:1 sfq perturb 10

DEV2=venet0

tc qdisc del dev \$DEV2 root tc qdisc add dev \$DEV2 root handle 1: cbq avpkt 1000 bandwidth 100mbit tc class add dev \$DEV2 parent 1: classid 1:1 cbq rate 1024kbit allot 1500 prio 5 bounded isolated tc filter add dev \$DEV2 parent 1: protocol ip prio 16 u32 match ip dst x.x.x.x flowid 1:1 tc qdisc add dev \$DEV2 parent 1:1 sfq perturb 10

This script limits the bandwidth for the ip x.x.x.x to 1024kbit/s both incoming and outgoing. It really works... Even if a client of yours use their vps to ddos, it will be stopped at 1024kbit/s, so if your machine has a 100mbit port it won't even affect your machine. Even if he gets ddos, it will also slow down the packages that comes to the machine and goes to the VPS. WARNING: From my own experience, I got one ip that was being ddosed, and it was slowing the entire VPS down, only the VPS, for it was limited. The problem is, I made the most stuppid thing and tried to delete the ip address. It wasn't a good choice, for the incoming ddos now was going to the host machine, for the ip address was already routed to go through the host machine. The packets went to the host machine and stopped there since they couldn't find the ip address they were originally going to. RESULT: the entire machine was affected... So if you guys get ddosed to 1 ip, just limit the bandwidth to 32kbit/s let's say and ask the DC to block it on the router, DO NOT delete the ip address or your entire machine will be affected.

Now, there is another script I'm using to check bandwidth used (incoming and outgoing). It's by using ip tables and thanks to someone else that have posted it.

You run it on the host machine...

#!/bin/bash DEV=eth0 iptables -A FORWARD -o \$DEV -s x.x.x.x iptables -A FORWARD -i \$DEV -d x.x.x.x

This will set the iptables to log the bandwidth used. Then it can be seen by using:

```
#!/bin/bash
iptables -L FORWARD -v -x
iptables -L FORWARD -v
```

The first line shows the real numbers in bytes, expanded. The second one shows the numbers in Kbyte or Mbyte... It will show something like:

```
pkts-bytes-target-prot-opt-in-out---source---destination 117K-18M-----all- -- -any-eth0-x.x.x.x--anywhere 114K-17M-----all- -- -eth0-any-anywhere-x.x.x.x
```

As you can see the second line shows outgoing bandwidth while the third line shows incoming bandwidth.

If you want to reset the counters, just use: iptables -Z

Hope this helped... And thanks for everything:)

Regards,

Eugenio Pacheco

Subject: Re: Bandwidth limiting crashes the machine Posted by jbond007 on Sat, 11 Aug 2007 11:11:14 GMT

View Forum Message <> Reply to Message

dear frind this error make me crazy [root@unknown ~]# tc qdisc del dev \$DEV root RTNETLINK answers: No such file or directory [root@unknown ~]#

please help me Thank you

Subject: Re: Bandwidth limiting crashes the machine Posted by vaverin on Sat, 11 Aug 2007 11:44:34 GMT

View Forum Message <> Reply to Message

This command required to drop old traffic shapping settings. However if traffic control has not been configured before -- you get this answer.

Just ignore it and run other commands.

Subject: Re: Bandwidth limiting crashes the machine Posted by jbond007 on Sat, 11 Aug 2007 12:20:55 GMT

View Forum Message <> Reply to Message

dear so if have RTNETLINK answers: No such file or directory i must ignore?
Thank you for your help' please reply!

how limit only 254 kb

Subject: Re: Bandwidth limiting crashes the machine Posted by vaverin on Sat, 11 Aug 2007 12:38:38 GMT

View Forum Message <> Reply to Message

jbond007 wrote on Sat, 11 August 2007 16:20dear so if have RTNETLINK answers: No such file or directory i must ignore?

Yes, if "tc qdisc del dev \$DEV root" returns

"RTNETLINK answers: No such file or directory"

you can ignore it. This message means that kernel do not have old settings for \$DEV device, and you can apply new settings.

Subject: Re: Bandwidth limiting crashes the machine Posted by jbond007 on Sat, 11 Aug 2007 14:45:38 GMT View Forum Message <> Reply to Message

Thank you for your help

how we test if work?

how i see the changes that i been made? Thank you