
Subject: [patch] util-linux-ng: unprivileged mounts support
Posted by [Miklos Szeredi](#) on Wed, 16 Jan 2008 12:38:53 GMT
[View Forum Message](#) <> [Reply to Message](#)

From: Miklos Szeredi <mszeredi@suse.cz>

This is an experimental patch for supporting unprivileged mounts and umounts. The following features are added:

1) If mount/umount are suid, first try without privileges.

This is done by forking, dropping privileges in child, and redirecting stderr to /dev/null. If this succeeds, then parent exits with zero exit code. Otherwise parent continues normally (with privileges). This isn't perfect, because the wrong error message will be printed if mount/umount failed not because of insufficient privileges, but some other error (e.g. mountpoint busy).

2) Support user mounts in kernel.

If /etc/mtab is a symlink (to /proc/mounts if it's been set up correctly), then change fsuid for the duration of the mount syscall and use the MS_SETOWNER flag. Old kernels will simply ignore this, and everything will work as before. Kernels with the unprivileged mounts patches will set the owner of the mount, and the relevant line in /proc/PID/mounts will contain a "user=XYZ" option, making this backward compatible with /etc/mtab.

3) Root can force a specific user for a mount with "-ouser=XYZ". This has worked previously as well, but that was probably just accidental (the option was copied verbatim to /etc/mtab).

4) Add support for "submnt" and "nosubmnt" options. These can be used to allow or prohibit unprivileged submounting of a user mount.

Example:

```
root# mount --bind -ouser=xyz /home/xyz /home/xyz
xyz> mount --bind ~/foo ~/bar
xyz> umount ~/bar
```

Changes since last version:

- rename options: 'nomnt' -> 'nosubmnt', 'mnt' -> 'submnt'
- change error message for EMFILE
- fix bug in handling 'user' option in /etc/fstab
- default to 'nosubmnt' for fstab based user mounts, for backward compatibility

Todo:

- proper error reporting for unprivileged mounts and umounts
- ./configure magic for non-linux systems

Signed-off-by: Miklos Szeredi <mszeredi@suse.cz>

Index: util-linux-ng/configure.ac

```
=====
--- util-linux-ng.orig/configure.ac 2008-01-16 11:30:34.000000000 +0100
+++ util-linux-ng/configure.ac 2008-01-16 11:31:48.000000000 +0100
@@ -92,6 +92,11 @@ fi
UTIL_CHECK_LIB(util, openpty)
UTIL_CHECK_LIB(termcap, tgetnum)

+UTIL_CHECK_LIB(cap, cap_get_proc)
+if test $have_cap = no; then
+ AC_MSG_ERROR([libcap is required for mount]);
+fi
+
AC_ARG_WITH([fsprobe],
  [AS_HELP_STRING([--with-fsprobe], [library to guess filesystems (blkid|volume_id), default is
blkid])],
  [], [with_fsprobe=blkid])
```

Index: util-linux-ng/mount/Makefile.am

```
=====
--- util-linux-ng.orig/mount/Makefile.am 2008-01-16 11:30:34.000000000 +0100
+++ util-linux-ng/mount/Makefile.am 2008-01-16 11:31:48.000000000 +0100
@@ -45,6 +45,10 @@ if HAVE_SELINUX
mount_LDADD += -lselinux
endif
```

```
+if HAVE_CAP
+mount_LDADD += -lcap
+endif
+
if HAVE_VOLUME_ID
utils_common += fsprobe_volumeid.c
swapon_SOURCES += ../lib/linux_version.c ../lib/blkdev.c
```

Index: util-linux-ng/mount/fsprobe.h

```
=====
--- util-linux-ng.orig/mount/fsprobe.h 2008-01-16 11:30:34.000000000 +0100
+++ util-linux-ng/mount/fsprobe.h 2008-01-16 11:31:48.000000000 +0100
@@ -33,6 +33,7 @@ struct mountargs {
const char *type;
int flags;
```

```
void *data;
+ uid_t uid;
};
```

```
extern int fsprobe_known_fstype_in_procfs(const char *type);
```

```
Index: util-linux-ng/mount/fstab.c
```

```
=====
```

```
--- util-linux-ng.orig/mount/fstab.c 2008-01-16 11:30:34.000000000 +0100
```

```
+++ util-linux-ng/mount/fstab.c 2008-01-16 11:31:48.000000000 +0100
```

```
@@ -47,7 +47,7 @@ mtab_does_not_exist(void) {
    return var_mtab_does_not_exist;
}
```

```
-static int
```

```
+int
```

```
mtab_is_a_symlink(void) {
    get_mtab_info();
    return var_mtab_is_a_symlink;
}
```

```
Index: util-linux-ng/mount/fstab.h
```

```
=====
```

```
--- util-linux-ng.orig/mount/fstab.h 2008-01-16 11:30:34.000000000 +0100
```

```
+++ util-linux-ng/mount/fstab.h 2008-01-16 11:31:48.000000000 +0100
```

```
@@ -2,6 +2,7 @@
```

```
#define MOUNT_FSTAB_H
```

```
#include "mount_mntent.h"
```

```
+int mtab_is_a_symlink(void);
```

```
int mtab_is_writable(void);
```

```
int mtab_does_not_exist(void);
```

```
int is_mounted_once(const char *name);
```

```
Index: util-linux-ng/mount/mount.c
```

```
=====
```

```
--- util-linux-ng.orig/mount/mount.c 2008-01-16 11:30:34.000000000 +0100
```

```
+++ util-linux-ng/mount/mount.c 2008-01-16 12:03:51.000000000 +0100
```

```
@@ -20,6 +20,8 @@
```

```
#include <sys/stat.h>
```

```
#include <sys/wait.h>
```

```
#include <sys/mount.h>
```

```
+#include <sys/fsuid.h>
```

```
+#include <sys/capability.h>
```

```
#include <mntent.h>
```

```
@@ -102,7 +104,7 @@ struct opt_map {
```

```
#define MS_USER 0x20000000
```

```
#define MS_OWNER 0x10000000
```

```
#define MS_GROUP 0x08000000
```

```
-#define MS_COMMENT 0x02000000
```

```

#define MS_COMMENT 0x04000000
#define MS_LOOP 0x00010000

/* Options that we keep the mount system call from seeing. */
@@ -114,10 +116,10 @@ struct opt_map {
#define MS_PROPAGATION (MS_SHARED|MS_SLAVE|MS_UNBINDABLE|MS_PRIVATE)

/* Options that we make ordinary users have by default. */
#define MS_SECURE (MS_NOEXEC|MS_NOSUID|MS_NODEV)
#define MS_SECURE (MS_NOEXEC|MS_NOSUID|MS_NODEV|MS_NOSUBMNT)

/* Options that we make owner-mounted devices have by default */
#define MS_OWNERSECURE (MS_NOSUID|MS_NODEV)
#define MS_OWNERSECURE (MS_NOSUID|MS_NODEV|MS_NOSUBMNT)

static const struct opt_map opt_map[] = {
    { "defaults", 0, 0, 0 }, /* default options */
@@ -177,6 +179,8 @@ static const struct opt_map opt_map[] =
    to mtime/ctime */
#endif
    { "nofail", 0, 0, MS_COMMENT}, /* Do not fail if ENOENT on dev */
+ { "submnt", 0, 1, MS_NOSUBMNT}, /* permit unprivileged submounts */
+ { "nosubmnt", 0, 0, MS_NOSUBMNT}, /* no unprivileged submounts */
    { NULL, 0, 0, 0 }
};

@@ -365,7 +369,7 @@ append_context(const char *optname, char
/* For the options uid= and gid= replace user or group name by its value.
*/
static inline void
-parse_opt(char *opt, int *mask, char **extra_opts) {
+parse_opt(char *opt, int *mask, char **extra_opts, char **user) {
    const struct opt_map *om;

    for (om = opt_map; om->opt != NULL; om++)
@@ -410,6 +414,11 @@ parse_opt(char *opt, int *mask, char **e
    return;
}
}
+ if (strncmp(opt, "user=", 5) == 0) {
+ free(*user);
+ *user = xstrdup(opt + 5);
+ return;
+ }

#ifdef HAVE_LIBSELINUX
    if (strncmp(opt, "context=", 8) == 0 && *(opt+8)) {
@@ -431,7 +440,7 @@ parse_opt(char *opt, int *mask, char **e

```

```

/* Take -o options list and compute 4th and 5th args to mount(2).  flags
   gets the standard options (indicated by bits) and extra_opts all the rest */
static void
-parse_opts (const char *options, int *flags, char **extra_opts) {
+parse_opts (const char *options, int *flags, char **extra_opts, char **user) {
    *flags = 0;
    *extra_opts = NULL;

@@ -454,7 +463,7 @@ parse_opts (const char *options, int *fl
    /* end of option item or last item */
    if (*p == '\0' || *(p+1) == '\0') {
        if (!parse_string_opt(opt))
-        parse_opt(opt, flags, extra_opts);
+        parse_opt(opt, flags, extra_opts, user);
        opt = NULL;
    }
}

@@ -525,6 +534,7 @@ create_mtab (void) {
    struct my_mntent mnt;
    int flags;
    mntFILE *mfp;
+ char *user = NULL;

    lock_mtab();

@@ -538,11 +548,11 @@ create_mtab (void) {
    /* Find the root entry by looking it up in fstab */
    if ((fstab = getfs_by_dir ("/") || (fstab = getfs_by_dir ("root")))) {
        char *extra_opts;
-        parse_opts (fstab->m.mnt_opts, &flags, &extra_opts);
+        parse_opts (fstab->m.mnt_opts, &flags, &extra_opts, &user);
        mnt.mnt_dir = "/";
        mnt.mnt_fsname = fsprobe_get_devname(fstab->m.mnt_fsname);
        mnt.mnt_type = fstab->m.mnt_type;
-        mnt.mnt_opts = fix_opts_string (flags, extra_opts, NULL);
+        mnt.mnt_opts = fix_opts_string (flags, extra_opts, user);
        mnt.mnt_freq = mnt.mnt_passno = 0;
        my_free(extra_opts);

@@ -564,6 +574,39 @@ create_mtab (void) {
        unlock_mtab();
    }

+static int set_fsuid(uid_t uid, uid_t *olduid)
+{
+    cap_t cap;
+    int res;
+

```

```

+ cap = cap_get_proc();
+ if (!cap) {
+   die(EX_FAIL, _("mount: failed to get capabilities: %s"),
+     strerror(errno));
+ }
+
+ res = setfsuid(uid);
+ if (olduid)
+   *olduid = res;
+
+ if (setfsuid(uid) != uid) {
+   error(_("mount: failed to set user"));
+   errno = EPERM;
+   return -1;
+ }
+
+ res = cap_set_proc(cap);
+ if (res == -1) {
+   die(EX_FAIL, _("mount: failed to restore capabilities"),
+     strerror(errno));
+ }
+
+ if (verbose > 2)
+   printf(_("mount: fsuid set to %i\n"), uid);
+
+ return 0;
+}
+
/* count successful mount system calls */
static int mountcount = 0;

@@ -575,16 +618,33 @@ static int mountcount = 0;
static int
do_mount_syscall (struct mountargs *args) {
    int flags = args->flags;
+   uid_t olduid = 0;
+   int res;

    if ((flags & MS_MGC_MSK) == 0)
        flags |= MS_MGC_VAL;

+   if (args->flags & MS_SETUSER) {
+       if (set_fsuid(args->uid, &olduid) == -1)
+           return -1;
+   }
+
    if (verbose > 2)
        printf("mount: mount(2) syscall: source: \"%s\", target: \"%s\", "

```

```

    "filesystemtype: \"%s\", mountflags: %d, data: %s\n",
    args->spec, args->node, args->type, flags, (char *) args->data);
+ res = mount(args->spec, args->node, args->type, flags, args->data);

- return mount (args->spec, args->node, args->type, flags, args->data);
+ if (args->flags & MS_SETUSER) {
+ int errno_save = errno;
+
+ if (set_fsuid(olduid, NULL) == -1)
+ die(EX_FAIL, _("mount: failed to restore fsuid"));
+
+ errno = errno_save;
+ }
+
+ return res;
}

/*
@@ -706,6 +766,31 @@ guess_fstype_by_devname(const char *devn
    return type;
}

+static int get_user(const char *user, uid_t *uid)
+{
+ char *e;
+ long val;
+ int res;
+
+ if (!user[0])
+ return -1;
+
+ val = strtoul(user, &e, 10);
+ if (!e[0]) {
+ if (val < 0 || (long) (uid_t) val != val)
+ return -1;
+
+ *uid = val;
+ } else {
+ struct passwd *pw = getpwnam(user);
+ if (pw == NULL)
+ return -1;
+
+ *uid = pw->pw_uid;
+ }
+ return 0;
+}
+
/*

```

```

* guess_fstype_and_mount()
* Mount a single file system. Guess the type when unknown.
@@ -715,8 +800,22 @@ guess_fstype_by_devname(const char *devn
*/
static int
guess_fstype_and_mount(const char *spec, const char *node, const char **types,
-    int flags, char *mount_opts, int *special, int *status) {
- struct mountargs args = { spec, node, NULL, flags & ~MS_NOSYS, mount_opts };
+    int flags, char *mount_opts, int *special, int *status,
+    char *user) {
+ struct mountargs args = { spec, node, NULL, flags & ~MS_NOSYS, mount_opts};
+
+ /*
+  * Only set user for the mount if /etc/mtab is a symlink. Otherwise
+  * user could add submounts without modifying mtab, and so cause
+  * confusion.
+  */
+ args.flags &= ~MS_SETUSER;
+ if (user != NULL && mtab_is_a_symlink()) {
+     if (get_user(user, &args.uid) != 0)
+         return 1;
+
+     args.flags |= MS_SETUSER;
+ }

    if (*types && strcasecmp(*types, "auto") == 0)
        *types = NULL;
@@ -770,6 +869,9 @@ guess_fstype_and_mount(const char *spec,
static void
suid_check(const char *spec, const char *node, int *flags, char **user) {
    if (suid) {
+     if (*user != NULL)
+         die(EX_USAGE, _("mount: only root can set user"));
+
        /*
         * MS_OWNER: Allow owners to mount when fstab contains
         * the owner option. Note that this should never be used
@@ -1057,7 +1159,7 @@ try_mount_one (const char *spec0, const
    char *extra_opts; /* written in mtab */
    char *mount_opts; /* actually used on system call */
    const char *opts, *spec, *node, *types;
- char *user = 0;
+ char *user = NULL;
    int loop = 0;
    const char *loopdev = 0, *loopfile = 0;
    struct stat statbuf;
@@ -1077,7 +1179,7 @@ try_mount_one (const char *spec0, const
    types = types1 = xstrdup(types0);

```



```

opts = opts1 = xstrdup(opts0);

- parse_opts (opts, &flags, &extra_opts);
+ parse_opts (opts, &flags, &extra_opts, &user);
  extra_opts1 = extra_opts;

/* quietly succeed for fstab entries that don't get mounted automatically */
@@ -1127,7 +1229,7 @@ try_mount_one (const char *spec0, const

  if (!fake) {
    mnt5_res = guess_fstype_and_mount (spec, node, &types, flags & ~MS_NOSYS,
-      mount_opts, &special, &status);
+      mount_opts, &special, &status, user);

    if (special) {
      block_signals (SIG_UNBLOCK);
@@ -1266,7 +1368,8 @@ try_mount_one (const char *spec0, const
      break;
    }
    case EMFILE:
-      error (_("mount table full")); break;
+      error (_("maximum number of user mounts exceeded,\n"
+        "see: /proc/sys/fs/max_user_mounts\n")); break;
    case EIO:
      error (_("mount: %s: can't read superblock"), spec); break;
    case ENODEV:
@@ -2011,10 +2114,43 @@ main(int argc, char *argv[]) {
  }

  if (getuid () != geteuid ()) {
-   suid = 1;
-   if (types || options || readwrite || nomtab || mount_all ||
-       fake || mounttype || (argc + specseen) != 1)
-     die (EX_USAGE, _("mount: only root can do that"));
+   int pid;
+
+   +
+   + pid = fork();
+   + if (pid == -1) {
+   +   die(EX_SYSERR, _("mount: cannot fork: %s"),
+   +     strerror(errno));
+   + } else if (pid == 0) {
+   +   /*
+   +    * Child will continue as normal, but first it
+   +    * drops privileges, and redirects stderr to
+   +    * /dev/null, because we will retry any error
+   +    * with the suid privileges.
+   +    */
+   +
  }

```

```
+ if (verbose > 1)
+     printf_("\nmount: trying without privileges...\n");
+
+ if(setgid(getgid()) == -1 ||
+     setuid(getuid()) == -1)
+     exit(1);
+
+ dup2(open("/dev/null", O_WRONLY), 2);
+ } else {
+     int st;
+
+     wait(&st);
+     if (WIFEXITED(st) && WEXITSTATUS(st) == 0)
+         exit(0);
+
+     suid = 1;
+     if (types || options || readwrite || nomtab ||
+         mount_all || fake || mounttype ||
+         (argc + specseen) != 1)
+         die(EX_USAGE, _("\nmount: only root can do that"));
+     if (verbose > 1)
+         printf_("\nmount: retrying with privileges...\n");
+ }
+ }
```

```

--- util-linux-ng/mount/mount_constants.h 2008-01-16 11:30:34.000000000 +0100
+++ util-linux-ng/mount/mount_constants.h 2008-01-16 11:31:48.000000000 +0100
@@ -56,6 +56,12 @@
#ifndef MS_SHARED
#define MS_SHARED (1<<20) /* 1048576 Shared*/
#endif
+
+#ifndef MS_SETUSER
+#define MS_SETUSER (1<<24)
+#endif
+
+#ifndef MS_NOSUBMNT
+#define MS_NOSUBMNT (1<<25)
+#endif
+
/*
 * Magic mount flag number. Had to be or-ed to the flag values.
 */

```

```
--- util-linux-ng.orig/mount/umount.c 2008-01-16 11:30:34.000000000 +0100
+++ util-linux-ng/mount/umount.c 2008-01-16 11:31:48.000000000 +0100
@@ -619,9 +619,42 @@ main (int argc, char *argv[]) {
```

```

    }

    if (getuid () != geteuid ()) {
-   suid = 1;
-   if (all || types || nomtab || force || remount)
-   die (2, _("umount: only root can do that"));
+   int pid;
+
+   pid = fork();
+   if (pid == -1) {
+   die(EX_SYSEERR, _("umount: cannot fork: %s"),
+       strerror(errno));
+   } else if (pid == 0) {
+   /*
+    * Child will continue as normal, but first it
+    * drops privileges, and redirects stderr to
+    * /dev/null, because we will retry any error
+    * with the suid privileges.
+    */
+
+   if (verbose)
+   printf(_("umount: trying without privileges...\n"));
+
+   if(setgid(getgid()) == -1 ||
+       setuid(getuid()) == -1)
+   exit(1);
+
+   dup2(open("/dev/null", O_WRONLY), 2);
+   } else {
+   int st;
+
+   wait(&st);
+   if (WIFEXITED(st) && WEXITSTATUS(st) == 0)
+   exit(0);
+
+   suid = 1;
+   if (all || types || nomtab || force || remount)
+   die (2, _("umount: only root can do that"));
+
+   if (verbose)
+   printf(_("umount: retrying with privileges...\n"));
+   }
    }

    argc -= optind;

```

Containers mailing list

Containers@lists.linux-foundation.org

Subject: Re: [patch] util-linux-ng: unprivileged mounts support
Posted by [Miklos Szeredi](#) on Wed, 16 Jan 2008 20:33:30 GMT
[View Forum Message](#) <> [Reply to Message](#)

> > This is an experimental patch for supporting unprivileged mounts and
> > umounts. The following features are added:
>
> same feedback as last time ... the cap stuff needs to be made optional and
> proper header checks added to configure ...

Later, sure. For now, I'm concentrating on the actual functionality.

> > 1) If mount/umount are suid, first try without privileges.
> >
> > This is done by forking, dropping privileges in child, and redirecting
> > stderr to /dev/null. If this succeeds, then parent exits with zero
> > exit code. Otherwise parent continues normally (with privileges).
> > This isn't perfect, because the wrong error message will be printed if
> > mount/umount failed not because of insufficient privileges, but some
> > other error (e.g. mountpoint busy).
>
> this normalization of error information does kind of suck ... but i
> think the way it's written, the end user will still get the real
> answer the second time around when the mount is attempted with root
> privs and not stderr sent to /dev/null ?

No, for example the user will get: "only root can umount foo" instead
of "foo is busy", which is very misleading, if the user `_can_ umount`
foo.

Miklos

Containers mailing list
Containers@lists.linux-foundation.org
<https://lists.linux-foundation.org/mailman/listinfo/containers>

Subject: Re: [patch] util-linux-ng: unprivileged mounts support
Posted by [Szabolcs Szakacsits](#) on Sat, 19 Jan 2008 16:05:15 GMT
[View Forum Message](#) <> [Reply to Message](#)

On Wed, 16 Jan 2008, Miklos Szeredi wrote:

> This is an experimental patch for supporting unprivileged mounts and

> umounts.

User unmount unfortunately still doesn't work if the kernel doesn't have the unprivileged mount support but as we discussed this in last July that shouldn't be needed for this case.

```
% mount -t ntfs-3g /dev/hda10 /tmp/test
% cat /proc/mounts | grep /tmp/test
/dev/hda10 /tmp/test fuseblk rw,nosuid,nodev,user_id=501,group_id=501,allow_other 0 0
% mount | grep /tmp/test
/dev/hda10 on /tmp/test type fuseblk (rw,nosuid,nodev,allow_other,blksize=1024,user=szaka)
% umount /tmp/test
umount: /dev/hda10: not mounted
umount: /tmp/test: must be superuser to umount
umount: /dev/hda10: not mounted
umount: /tmp/test: must be superuser to umount
```

Szaka

--

NTFS-3G: <http://ntfs-3g.org>

Containers mailing list
Containers@lists.linux-foundation.org
<https://lists.linux-foundation.org/mailman/listinfo/containers>

Subject: Re: [patch] util-linux-ng: unprivileged mounts support
Posted by [Miklos Szeredi](#) on Sat, 19 Jan 2008 20:32:22 GMT
[View Forum Message](#) <> [Reply to Message](#)

> > This is an experimental patch for supporting unprivileged mounts and
> > umounts.
>
> User unmount unfortunately still doesn't work if the kernel doesn't have
> the unprivileged mount support but as we discussed this in last July that
> shouldn't be needed for this case.
>
> % mount -t ntfs-3g /dev/hda10 /tmp/test
> % cat /proc/mounts | grep /tmp/test
> /dev/hda10 /tmp/test fuseblk rw,nosuid,nodev,user_id=501,group_id=501,allow_other 0 0
> % mount | grep /tmp/test
> /dev/hda10 on /tmp/test type fuseblk (rw,nosuid,nodev,allow_other,blksize=1024,user=szaka)
> % umount /tmp/test
> umount: /dev/hda10: not mounted
> umount: /tmp/test: must be superuser to umount
> umount: /dev/hda10: not mounted
> umount: /tmp/test: must be superuser to umount

But 'fusermount -u /tmp/test' does work, doesn't it?

Yes, this should probably be fixed in umount(8), but it's an (almost) completely separate issue.

Miklos

Containers mailing list
Containers@lists.linux-foundation.org
<https://lists.linux-foundation.org/mailman/listinfo/containers>

Subject: Re: [patch] util-linux-ng: unprivileged mounts support
Posted by [Szabolcs Szakacsits](#) on Sat, 19 Jan 2008 21:42:33 GMT
[View Forum Message](#) <> [Reply to Message](#)

On Sat, 19 Jan 2008, Miklos Szeredi wrote:

>
> But 'fusermount -u /tmp/test' does work, doesn't it?

You're submitting patches to get rid of fusermount, aren't you?

Most users absolutely have no idea what fusermount is and they would
__really__ like to see umount(8) working finally.

Szaka

--
NTFS-3G: <http://ntfs-3g.org>

Containers mailing list
Containers@lists.linux-foundation.org
<https://lists.linux-foundation.org/mailman/listinfo/containers>
