Subject: NAT enabled but VE cannot communicate beyond HN Posted by cheuschober on Sun, 13 May 2007 05:29:28 GMT View Forum Message <> Reply to Message

Hi. I have a HN with two NIC's (eth0=172.16.192.XX,eth1=172.16.192.YY). One of the NIC's (eth0) I'm reserving exclusively for a specific type of high-availability lan traffic. The other NIC (eth1) I want to handle all of my VE traffic.

In the case of my VE's I'm trying to run them on a different domain (172.16.91.---). As instructed by the wiki I set up a NAT route for traffic over eth1 for the VE (in this case a very generous route for debugging):

\$ iptables -t nat -A POSTROUTING -o eth1 -j SNAT --to 172.16.192.YY

The HN and the VE can communicate with or without the route but I cannot get the LAN (or WAN) outside the HN to communicate to the VE or visa/versa.

At this point I'm not certain what I'm doing wrong so any guidance or help is appreciated. If I assign the VE on the same net as the HN (eg, 172.16.192.ZZ) I can communicate to the LAN and WAN with or without trouble (or a NAT entry for that matter) so I take that to mean this has something to do with NAT but I don't quite know what.

Again, any and all help is appreciated.

HN, \$ ip a l

- 2: lo: <LOOPBACK,UP,10000> mtu 16436 qdisc noqueue link/loopback 00:00:00:00:00 brd 00:00:00:00:00 inet 127.0.0.1/8 scope host lo inet6 ::1/128 scope host valid_lft forever preferred_lft forever
- 4: sit0: <NOARP> mtu 1480 qdisc noop link/sit 0.0.0.0 brd 0.0.0.0
- 6: eth0: <BROADCAST,MULTICAST,UP,10000> mtu 1500 qdisc pfifo_fast qlen 1000 link/ether 00:15:17:19:17:68 brd ff:ff:ff:ff: inet 172.16.192.50/24 brd 172.16.192.255 scope global eth0 inet6 fe80::215:17ff:fe19:1768/64 scope link valid_lft forever preferred_lft forever

8: eth1: <BROADCAST,MULTICAST,UP,10000> mtu 1500 qdisc pfifo_fast qlen 100 link/ether 00:15:17:19:17:69 brd ff:ff:ff:ff: inet 172.16.192.60/24 brd 172.16.192.255 scope global eth1 inet6 fe80::215:17ff:fe19:1769/64 scope link valid_lft forever preferred_lft forever

7: venet0: <BROADCAST,POINTOPOINT,NOARP,UP,10000> mtu 1500 qdisc noqueue link/void

HN, /etc/sysctl.conf net.ipv4.conf.all.rp_filter=1 net.ipv4.conf.eth1.forwarding=1 net.ipv4.ip_forward=1 net.ipv4.conf.eth1.proxy_arp=0 net.ipv4.tcp_ecn=0 net.ipv4.conf.eth1.send_redirects=1 net.ipv4.conf.all.send_redirects=0 net.ipv4.conf.all.arp_ignore=1 net.ipv4.conf.all.arp_announce=2 net.ipv4.conf.default.forwarding=1 net.ipv4.conf.default.proxy_arp = 0 net.ipv4.conf.all.rp_filter = 1 net.ipv4.conf.default.send_redirects = 1 net.ipv4.conf.all.send_redirects = 0

Page 2 of 2 ---- Generated from OpenVZ Forum