
Subject: *SOLVED* Unable to set iptables on running VE
Posted by [pringleso](#) on Wed, 16 May 2007 17:17:52 GMT
[View Forum Message](#) <> [Reply to Message](#)

hello,

I want to give VPN access through a VE, but the only problem i'm having is that i can't NAT inside the VE.

Referring to this thread http://forum.openvz.org/index.php?t=msg&goto=11904&& amp; amp; amp; amp; amp; srch=nat+inside+ve#msg_11904

I tried

```
[root@myServer ~]# vzctl set 111 --iptables iptable_nat --save
Unable to set iptables on running VE
Saved parameters for VE 111
```

myServer=HN

:'(

```
[root@myServer ~]# lsmod | grep ^iptables
iptables          26296  1
```

can anybody help?

thanks

edit:

added iptable_nat to vz.conf but doesnt make a diff

```
[root@fc61484 vz]# cat vz.conf
## Global parameters
VIRTUOZZO=yes
LOCKDIR=/vz/lock
DUMPDIR=/vz/dump
VE0CPUUNITS=15000

## Logging parameters
LOGGING=yes
LOGFILE=/var/log/vzctl.log
```

```
LOG_LEVEL=0
VERBOSE=0
```

```
## Disk quota parameters
DISK_QUOTA=yes
VZFASTBOOT=no
```

```
# The name of the device whose ip address will be used as source ip for VE.
# By default automatically assigned.
#VE_ROUTE_SRC_DEV="eth0"
```

```
## Template parameters
TEMPLATE=/vz/template
```

```
## Defaults for VEs
VE_ROOT=/vz/root/$VEID
VE_PRIVATE=/vz/private/$VEID
CONFIGFILE="vps.basic"
DEF_OSTEMPLATE="fedora-core-4"
```

```
## Load vzwdog module
VZWDOG="no"
IPV6="no"
```

```
IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle ipt_TCPMSS
ipt_tcpmss ipt_ttl ipt_length iptable_nat"
```

then restarted /etc/init.d/vz fine

```
[root@myServer ~]# vzctl set 111 --iptables iptable_nat --save
Unable to set iptables on running VE
Saved parameters for VE 111
```

```
[root@myServer]# route -n
Kernel IP routing table
Destination Gateway Genmask Flags Metric Ref Use Iface
192.168.2.111 0.0.0.0 255.255.255.255 UH 0 0 0 venet0
216.x.x.x 0.0.0.0 255.255.255.128 U 0 0 0 eth0
169.254.0.0 0.0.0.0 255.255.0.0 U 0 0 0 eth0
0.0.0.0 216.x.x.x 0.0.0.0 UG 0 0 0 eth0
```

inside the VE:

```
root@vps111:~# route -n
```

```
Kernel IP routing table
```

Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
192.0.2.1	0.0.0.0	255.255.255.255	UH	0	0	0	venet0
10.8.0.2	0.0.0.0	255.255.255.255	UH	0	0	0	tun0
10.8.0.0	10.8.0.2	255.255.255.0	UG	0	0	0	tun0
0.0.0.0	192.0.2.1	0.0.0.0	UG	0	0	0	venet0

```
root@vps111:~# iptables -t nat -A POSTROUTING -s 10.8.0.6 -o eth0 -j SNAT --to 192.0.2.1
```

```
root@vps111:~# route -n
```

```
Kernel IP routing table
```

Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
192.0.2.1	0.0.0.0	255.255.255.255	UH	0	0	0	venet0
10.8.0.2	0.0.0.0	255.255.255.255	UH	0	0	0	tun0
10.8.0.0	10.8.0.2	255.255.255.0	UG	0	0	0	tun0
0.0.0.0	192.0.2.1	0.0.0.0	UG	0	0	0	venet0

10.8.0.6 is the ip given to a computer on the vpn, the VE is able to ping the computer connected via vpn and vice versa.