
Subject: Help in DHCP Server

Posted by [f.sivas](#) on Thu, 10 Jun 2010 15:14:27 GMT

[View Forum Message](#) <> [Reply to Message](#)

I have a Debian 5.0 machine with linux-image-2.6.26-2-openvz-686.

With 2 network cards. One is eth0 connected to the modem, the other is eth1 with a static ip (192.168.1.9) connected to an wireless access point.

At the moment i've got in the node the DHCP Server running because i can't configure it in a virtual machine. What i did was:

First off all stop the dhcp server in the hardware node and unconfigure eth1.

```
[host-node]:~# ifconfig -a
```

```
eth0    Link encap:Ethernet HWaddr xx:xx:xx:xx:xx:xx  
        inet addr:xxx.xxx.xxx.xxx Bcast:xxx.xxx.xxx.xxx Mask:255.255.240.0  
        inet6 addr: fe80::221:85ff:fe15:bedf/64 Scope:Link  
              UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1  
              RX packets:5320 errors:0 dropped:0 overruns:0 frame:0  
              TX packets:3222 errors:0 dropped:0 overruns:0 carrier:0  
              collisions:0 txqueuelen:1000  
              RX bytes:6549594 (6.2 MiB) TX bytes:326786 (319.1 KiB)  
              Interrupt:221
```

```
eth1    Link encap:Ethernet HWaddr xx:xx:xx:xx:xx:xx  
          BROADCAST MULTICAST MTU:1500 Metric:1  
          RX packets:0 errors:0 dropped:0 overruns:0 frame:0  
          TX packets:0 errors:0 dropped:0 overruns:0 carrier:0  
          collisions:0 txqueuelen:1000  
          RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)  
          Interrupt:16 Base address:0xe800
```

```
lo     Link encap:Local Loopback  
        inet addr:127.0.0.1 Mask:255.0.0.0  
        inet6 addr: ::1/128 Scope:Host  
              UP LOOPBACK RUNNING MTU:16436 Metric:1  
              RX packets:0 errors:0 dropped:0 overruns:0 frame:0  
              TX packets:0 errors:0 dropped:0 overruns:0 carrier:0  
              collisions:0 txqueuelen:0  
              RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)
```

```
venet0  Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00  
        UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1  
        RX packets:2459 errors:0 dropped:0 overruns:0 frame:0  
        TX packets:4428 errors:0 dropped:0 overruns:0 carrier:0  
        collisions:0 txqueuelen:0  
        RX bytes:143700 (140.3 KiB) TX bytes:6383660 (6.0 MiB)
```

Then add veth device to CT

```
[host-node]:~# vzctl set 107 --netif_add eth1 --save
```

```
[host-node]:~# ifconfig -a
```

```
eth0    Link encap:Ethernet HWaddr xx:xx:xx:xx:xx:xx
        inet addr:xxx.xxx.xxx.xxx Bcast:xxx.xxx.xxx.xxx Mask:255.255.240.0
        inet6 addr: fe80::221:85ff:fe15:bedf/64 Scope:Link
        UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
        RX packets:5414 errors:0 dropped:0 overruns:0 frame:0
        TX packets:3254 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:1000
        RX bytes:6575652 (6.2 MiB) TX bytes:333920 (326.0 KiB)
        Interrupt:221

eth1    Link encap:Ethernet HWaddr xx:xx:xx:xx:xx:xx
        BROADCAST MULTICAST MTU:1500 Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:1000
        RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)
        Interrupt:16 Base address:0xe800

lo     Link encap:Local Loopback
        inet addr:127.0.0.1 Mask:255.0.0.0
        inet6 addr: ::1/128 Scope:Host
        UP LOOPBACK RUNNING MTU:16436 Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)

venet0  Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1
        RX packets:2503 errors:0 dropped:0 overruns:0 frame:0
        TX packets:4472 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:147327 (143.8 KiB) TX bytes:6387674 (6.0 MiB)

veth107.1 Link encap:Ethernet HWaddr xx:xx:xx:xx:xx:xx
        inet6 addr: fe80::218:51ff:fea1:8375/64 Scope:Link
        UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)
```

Then configure device in CT

```
[host-node]# ifconfig veth107.1 0
[host-node]# echo 1 > /proc/sys/net/ipv4/conf/veth107.1/forwarding
[host-node]# echo 1 > /proc/sys/net/ipv4/conf/veth107.1/proxy_arp
[host-node]# echo 1 > /proc/sys/net/ipv4/conf/eth1/forwarding
[host-node]# echo 1 > /proc/sys/net/ipv4/conf/eth1/proxy_arp
```

Configure device in CT107

```
[ve-101]# ifconfig eth1 0
[ve-101]# ip addr add 192.168.1.9 dev eth1
[ve-101]# ip route add default dev eth1
# RTNETLINK answers: File exists
dhcp:/# ip route
192.0.2.1 dev venet0 scope link
default via 192.0.2.1 dev venet0
[ve-101]# ip route del default via 192.0.2.1 dev venet0
[ve-101]# ip route add default dev eth1
```

Add route in CT0

```
[host-node]# ip route add 192.168.1.9 dev veth107.1
```

After this

```
[ve-101]# apt-get install dhcpc3-server
```

The strange is that i can ping 192.168.1.9 but the clients can't get any leases.

Can someone help me in the configuration?

Thanks.
