
Subject: Re: Quotas / Disk Space

Posted by [Mishin Dmitry](#) on Tue, 07 Nov 2006 08:35:06 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi, Douglas!

Answers are inline.

On Friday 03 November 2006 23:19, Douglas Phillips wrote:

> First of all, this is my first post to the list. I've tried to do
> some research and investigation on this, but at this point have not
> found anything useful.

>

> Here's the scenario:

> Customer using OpenVZ, RHEL 4 Update 3, Kernel 2.6.9-023stab016.2-smp
I advice to upgrade to newer 2.6.9 kernel - it is much more stable, than this.

> They tell me that they have 200G of space on the drive, and there is
> one partition that is not mounted, but when I try to mount comes up
> with "/dev/hda6 already mounted or /mnt/test busy".

>

> I'm assuming that VZ is using that partition in a raw format,
> although I have no specific information that I've found that confirms
> that. Am I correct?

No, OpenVZ doesn't use raw partitions.

>

> Mount points on the host machine are as follows:

> [root@(machine) ~]# df -h

Filesystem	Size	Used	Avail	Use%	Mounted on
/dev/hda3	20G	9.1G	9.7G	49%	/
/dev/hda1	99M	45M	50M	48%	/boot
none	1008M	0	1008M	0%	/dev/shm
/dev/hda2	20G	13G	5.8G	70%	/var
/dev/mapper/vps-swap	20G	18G	1.7G	92%	/srv/vservers/swap

This is probably an answer - /dev/hda6 is used as a part of LVM group.

> [root@(machine) ~]# mount

> /dev/hda3 on / type ext3 (rw)

> none on /proc type proc (rw)

> none on /sys type sysfs (rw)

> none on /dev/pts type devpts (rw,gid=5,mode=620)

> /dev/hda1 on /boot type ext3 (rw)

> none on /dev/shm type tmpfs (rw)

> /dev/hda2 on /var type ext3 (rw)

> /dev/mapper/vps-swap on /srv/vservers/swap type ext3 (rw)

> [root@(machine) ~]#

>

> The problem is as follows:

> There are 6 VEs currently running on the system, 4 with quotas set at
> 11GB, 1 at 5GB, and the one in question which was at 5GB, but which I
> upped to 20GB. When I "rebooted" this VPS, #102, and I go back, the
> quota stat shows quota back at 5GB.
Probably, you upped quota without --save flag. You could check this by `grep
DISKSPACE /etc/vz/conf/102.conf` command.

>
> The internal df output shows the following:
> bash-3.00# df -h
> Filesystem Size Used Avail Use% Mounted on
> simfs 3.4G 699M 1.7G 30% /
> tmpfs 1008M 0 1008M 0% /dev/shm
> tmpfs 1008M 0 1008M 0% /dev/shm
> bash-3.00#

>
> The desired result is that the filesystem would have 20GB available
> to it. Obviously that's not happening. Since I am not familiar with
> OpenVZ, I'd like to get some suggestions from the community on where
> I should look to resolve the issue.

>
> Thanks in advance,
>
> --
> Douglas G. Phillips
> Simple Business Solutions
--
Thanks,
Dmitry.
