
Subject: automatic veth setup

Posted by [Bowser Bizowser](#) on Wed, 11 Oct 2006 16:12:30 GMT

[View Forum Message](#) <> [Reply to Message](#)

I'm trying to setup a veth only server, and I think I'm just about there. The new vznetcfg script is helpful for setting up the vethX.0 interface when running vzctl start. I have modified this script to setup forwarding & proxy arp as well. I would like to assign the route at the same time, but if I specify IP_ADDRESS in the .conf file, it tries to assign it to venet (which isn't there) and fails. I'm not sure what other place would be good to stick the ip. It seems like the vznetcfg is the place to setup the route, as it is after vethX.0 has been setup on the host, but still runs in the host context. (using a .mount script wouldn't work because vethX.0 isn't up yet)

It seems like the infrastructure for veth is still being worked out.. Is there a standard way to set this up that I'm missing?

Subject: Re: automatic veth setup

Posted by [dev](#) on Fri, 13 Oct 2006 08:23:58 GMT

[View Forum Message](#) <> [Reply to Message](#)

AFAICS,

vznetcfg is to configure host end of veth device.
you can put it into the bridge or setup the routing - whatever you want.
Just add routing with something like:
`# ip r a <ve ip> dev <out-device>`

However, the second veth device in VE should be configured as well.
And this can be done with srd distribution scripts.
for example, in Redhat based distributions you can create appropriate ifcfg-vethX file with settings.

Kirill

> I'm trying to setup a veth only server, and I think I'm just about
> there. The new vznetcfg script is helpful for setting up the vethX.0
> interface when running vzctl start. I have modified this script to
> setup forwarding & proxy arp as well. I would like to assign the route
> at the same time, but if I specify IP_ADDRESS in the .conf file, it
> tries to assign it to venet (which isn't there) and fails. I'm not
> sure what other place would be good to stick the ip. It seems like the
> vznetcfg is the place to setup the route, as it is after vethX.0 has
> been setup on the host, but still runs in the host context. (using a
> .mount script wouldn't work because vethX.0 isn't up yet)
>

> It seems like the infrastructure for veth is still being worked out..
> Is there a standard way to set this up that I'm missing?
>
>
>
> -----
>
>

Subject: Re: automatic veth setup
Posted by [Bowser Bizowser](#) on Fri, 13 Oct 2006 12:51:16 GMT
[View Forum Message](#) <> [Reply to Message](#)

On 10/13/06, Kirill Korotaev <dev@sw.ru> wrote:

>
> AFAICS,
>
> vznetcfg is to configure host end of veth device.
> you can put it into the bridge or setup the routing - whatever you want.
> Just add routing with something like:
> # ip r a <ve ip> dev <out-device>

How to add routing isn't so much of the problem, but where to add it, and where to get the ip used to add it. The above ip command should work fine, and I'm fine with putting it in the vznetcfg script, but the question is "where do I get the veip from?" Like I said, it seems the IP_ADDRESS in the .conf would be the place for it. However, with the ip there, it tries to add to venet, and the vps _does not start_ without the venet interface setup. I could create another variable for the IP, or get it in another roundabout fashion, but it seems that there should be an elegant way for vznetcfg to get the ip. Even a way to disable IP_ADDRESS from being added to venet would work. (or a way that causes it to just fail at venet network setup instead of preventing the vps from starting at all).

However, the second veth device in VE should be configured as well.

> And this can be done with srd distribution scripts.
> for example, in Redhat based distributions you can
> create appropriate ifcfg-vethX file with settings.

I have no problems setting up the interface on the VE side.
