
Subject: Re: Split VE disk space between / and /var?
Posted by [Jan Tomasek](#) on Thu, 31 Jan 2008 07:34:12 GMT
[View Forum Message](#) <> [Reply to Message](#)

Kirill Korotaev wrote:

```
>> chlivek:~# vzctl stop 192003
>> Stopping VE ...
>> VE was stopped
>> + ls -l /staj/vz/root/192003/mnt
>> total 0
>> + umount /staj/vz/root/192003/mnt
>> umount: /staj/vz/private/192003.mnt: not mounted
>> umount: /staj/vz/private/192003.mnt: not mounted
>
> that's because VE distro specific init scripts do umount of everything on stop.
> so you can ignore this warning (but leave umount just in case).
```

Ok. I modified my umount script to not show errors:

```
#!/bin/bash -x
```

```
umount /staj/vz/root/192003/mnt 2>/dev/null
vzquota off 10192003
```

```
>> Mount point /staj/vz/root/192003/mnt doesn't exist at moment of calling.
>> But when I do not call umout it hangs in system mount tab.
>
> check -n option to mount.
```

Great. Thanks!

```
>> I'm also interested if it's posible to have inside VE df showing correct
>> info, instead of total HW node capacity.
>>
>> root@dns:/# df -h
>> Filesystem      Size  Used Avail Use% Mounted on
>> simfs           1.0G  370M  655M  37% /
>> /dev2/root2      1.1T   46G 1020G   5% /mnt
>> tmpfs            4.0G    0 4.0G   0% /lib/init/rw
>> tmpfs            4.0G    0 4.0G   0% /dev/shm
>
> have you called vzquota on on this directory?
> plz check vzquota init, on, off commands.
> you will need to assign some numerical ID to this quota directory (should be different from
VEID),
> setup vzquota on it and simply turn it on before bind mount.
```

Yes I did initialized quota by:

```
# vzquota init 10192003 -p /staj/vz/private/192003.mnt -b 1000 -B 1500  
-i 100 -l 150 -e 0 -n 0
```

and I'm activating in mount script:

```
#!/bin/bash -x
```

```
vzquota on 10192003  
mount -n --bind /staj/vz/private/192003.mnt /staj/vz/root/192003/mnt
```

It's working:

```
chlivek:~# vzctl enter 192003  
entered into VE 192003  
root@dns:/# echo "test" >/mnt/test  
-bash: echo: write error: Disk quota exceeded
```

but df still show it as

```
>> /dev2/root2      1.1T  46G 1020G   5% /mnt
```

which isn't very intuitive and for me as admin should be really better
to be able hide total system capacity from my users :)

Any idea how to solve this?

--

Jan Tomasek aka Semik
<http://www.tomasek.cz/>
