
Subject: ping impossible entre HN et VE et vice-versa

Posted by [ineza](#) on Thu, 12 Jan 2012 18:15:21 GMT

[View Forum Message](#) <> [Reply to Message](#)

bonjour,

j'ai un serveur debian squeeze amd64 où je dois installer 3 services virtualisés.

j'ai suivi le tuto du site OpenVZ, mais en choisissant d'utiliser l'interface veth en bridge, je ne parviens pas à faire fonctionner la communication réseau entre le HN et les VE,

voir les fichiers de configurations:

1) sur le HN : root@serveurmail:~# cat /etc/network/interfaces

```
# This file describes the network interfaces available on your system
# and how to activate them. For more information, see interfaces(5).
```

```
# The loopback network interface
```

```
auto lo
```

```
iface lo inet loopback
```

```
# The primary network interface
```

```
auto eth0 #interface connecté sur le réseau principal
```

```
#allow-hotplug eth0
```

```
iface eth0 inet static
```

```
address 10.24.1.185
```

```
network 10.24.0.0
```

```
netmask 255.255.240.0
```

```
broadcast 10.24.15.255
```

```
gateway 10.24.1.254
```

```
pre-up iptables-restore < /etc/iptables/iptables-active
```

```
auto eth1
```

```
allow-hotplug eth1
```

```
# eth 1:interface sur lequel j'aun un sous réseau recevant des IP en dhcp
```

```
iface eth1 inet static
```

```
address 192.168.8.1
```

```
network 192.168.8.0
```

```
netmask 255.255.255.0
```

```
broadcast 192.168.8.255
```

```
auto eth3 # interface juste pr administrer mn HN
```

```
allow-hotplug eth3
```

```
iface eth3 inet static
```

```
address 192.168.10.15
network 192.168.10.0
netmask 255.255.255.0
broadcast 192.168.10.255
```

```
auto vz1 #interface virtuel servant de pont sur le eth2
iface vz1 inet manual
    bridge_ports eth2
```

```
auto veth153.0 #interface virtuel pr le VE 153
iface veth153.0 inet static
address 10.24.1.187
network 10.24.0.0
netmask 255.255.240.0
broadcast 10.24.15.255
gateway 10.24.1.254
```

2) dans le VE 153 la configuration réseau est :

```
auto eth0
iface eth0 inet static
    address 10.24.1.188
    network 10.24.0.0
    netmask 255.255.240.0
    broadcast 10.24.15.255
    gateway 10.24.1.187
```

Je ne parviens pas à faire des pings du HN vers le VE ni l'inverse

help!

cordialement
