Subject: How to stop the VE during service vz stop
Posted by ccto on Wed, 07 Nov 2012 17:43:22 GMT
View Forum Message <> Reply to Message

Hello All,

in the past, as I remember, if we stop the vz service (service vz stop), it will automatically stop all VE containers accordingly.

Now, updated to the latest kernel, and vzctl, when we stop the vz, it will suspend all the VE(s), instead of stopping them.

May I know anyway to make stop all the VE(s) when the vz service stop?

I am afraid when we update the ovzkernel, it cannot resume the VE after reboot, and cause the mysql inside VE sudden poweroff , and cause an inconsistent state.

Please advise.

Thank you for your kind attention.

Subject: Re: How to stop the VE during service vz stop
Posted by JAlbstmeijer on Fri, 09 Nov 2012 08:34:29 GMT
View Forum Message <> Reply to Message

Hi,

I would be in favor too of an option to change the default '/etc/init.d/vz stop' behavior from 'suspend' to 'stop'.

Maybe even per ct.

J.

Subject: Re: How to stop the VE during service vz stop
Posted by AlexAT on Tue, 04 Dec 2012 22:39:54 GMT
View Forum Message <> Reply to Message

I'm 3rd here.

Suspending utilize more resources for suspending and unsuspending so my busy servers have MUCH more downtime for each standard reboot - tens of minutes instead of few minutes in case of stop/start.
So now server rebooting is not just "reboot -n" but "vzctl stop EACH ct, then run reboot".

Is it possible to tune this to have "stop" not "suspend" ?

Subject: Re: How to stop the VE during service vz stop
Posted by mperkel on Fri, 07 Dec 2012 10:49:38 GMT
View Forum Message <> Reply to Message

In the /etc/init.d/vz file I changed:

stages="suspend stop"

to

stages="stop"

Subject: Re: How to stop the VE during service vz stop
Posted by mperkel on Fri, 07 Dec 2012 17:45:43 GMT
View Forum Message <> Reply to Message

Try upgrading to the 4.1.1 release.

Subject: Re: How to stop the VE during service vz stop
Posted by AlexAT on Tue, 11 Dec 2012 20:39:09 GMT
View Forum Message <> Reply to Message

I tried both 4.1.1 and 4.1.1-1.
"service vz stop" still suspend VEs.

rpm -qa | grep vz
ovzkernel-2.6.18-308.8.2.el5.028stab101.1
vzctl-4.1.1-1
vzquota-3.1-1
ovzkernel-devel-2.6.18-308.8.2.el5.028stab101.1
vzctl-core-4.1.1-1

Subject: Re: How to stop the VE during service vz stop
Posted by ccto on Wed, 12 Dec 2012 02:24:00 GMT
View Forum Message <> Reply to Message

You need to add
VE_STOP_MODE="stop"

into /etc/vz/vz.conf