
Subject: [PATCH] Remove unused variables from fs/proc/base.c
Posted by [Pavel Emelianov](#) on Thu, 23 Aug 2007 15:43:19 GMT
[View Forum Message](#) <> [Reply to Message](#)

When removing the explicit task_struct->pid usage I found that proc_readfd_common() and proc_pident_readdir() get this field, but do not use it at all. So this cleanup is a cheap help with the task_struct->pid isolation.

Signed-off-by: Pavel Emelianov <xemul@openvz.org>

fs/proc/base.c | 5 +----
1 files changed, 1 insertion(+), 4 deletions(-)

```
diff --git a/fs/proc/base.c b/fs/proc/base.c
index 2fb3dfc..79e1918 100644
--- a/fs/proc/base.c
+++ b/fs/proc/base.c
@@ -1434,7 +1434,7 @@ static int proc_readfd_common(struct fil
     struct dentry *dentry = filp->f_path.dentry;
     struct inode *inode = dentry->d_inode;
     struct task_struct *p = get_proc_task(inode);
-    unsigned int fd, tid, ino;
+    unsigned int fd, ino;
     int retval;
     struct files_struct *files;
     struct fdtable *fdt;
@@ -1443,7 +1443,6 @@ static int proc_readfd_common(struct fil
     if (!p)
         goto out_no_task;
     retval = 0;
-    tid = p->pid;

     fd = filp->f_pos;
     switch (fd) {
@@ -1678,7 +1677,6 @@ static int proc_pident_readdir(struct fi
     const struct pid_entry *ents, unsigned int nents)
     {
         int i;
-        int pid;
         struct dentry *dentry = filp->f_path.dentry;
         struct inode *inode = dentry->d_inode;
         struct task_struct *task = get_proc_task(inode);
@@ -1691,7 +1689,6 @@ static int proc_pident_readdir(struct fi
         goto out_no_task;
```

```
ret = 0;  
- pid = task->pid;  
i = filp->f_pos;  
switch (i) {  
case 0:
```

Containers mailing list

Containers@lists.linux-foundation.org

<https://lists.linux-foundation.org/mailman/listinfo/containers>
