
Posted by [weldpua2008](#) on Fri, 08 Dec 2006 21:27:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
# vzctl exec 555 cat /proc/cpuinfo
processor      : 0
model name    : Pentium II (Deschutes)
cpu MHz       : 102.720
```

```
# cat /proc/cpuinfo
processor      : 0
model name    : Pentium II (Deschutes)
cpu MHz       : 342.625
```

Posted by [dim](#) on Fri, 08 Dec 2006 23:12:44 GMT

[View Forum Message](#) <> [Reply to Message](#)

Posted by [weldpua2008](#) on Sat, 09 Dec 2006 00:29:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
# vzcpucheck -v
vpsid      units
```

```
-----
0          1000
```

```
555        18518
```

```
Current CPU utilization: 19518
```

```
Power of the node: 17275
```

```
Warning: hardware node is overcommitted
```

```
# vzctl set 555 --cpuunits 18000 --cpulimit 130 --save
```

```
Setting CPU limit: 130
```

```
Setting CPU units: 18000
```

Power of the node: 17275

Posted by [weldpua2008](#) on Sat, 09 Dec 2006 10:28:27 GMT
[View Forum Message](#) <> [Reply to Message](#)

vzcpucheck
Power of the node: 17275

->cpuunits?

Posted by [dim](#) on Mon, 11 Dec 2006 11:13:43 GMT
[View Forum Message](#) <> [Reply to Message](#)

cpuunits_2 = 1000.

Posted by [weldpua2008](#) on Sun, 24 Dec 2006 21:45:59 GMT
[View Forum Message](#) <> [Reply to Message](#)

cpuunits_2 = 1000.

#vzcpucheck
Current CPU utilization: 2000
Power of the node: 17275

Posted by [sHaggY_caT](#) on Wed, 03 Feb 2010 07:58:51 GMT
[View Forum Message](#) <> [Reply to Message](#)

weldpua2008 wrote on Sun, 24 December 2006 16:45

Ve101:
cpulimit 15
cpuunits 10000

ve102
cpulimit 80
cpuunits 100

