
Subject: bond+vlan

Posted by [sa10](#) on Thu, 12 Jul 2007 11:14:33 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
VE0
eth0  eth1
 \    /
  bond0
 /    \
vlan5   br5(bridge)
        |
        ve102.0 (veth)
        |
VE111   eth0 (ve102.0)--vlan36
```

brctl show

bridge name	bridge id	STP enabled	interfaces
br5	8000.00123456789b	no	bond0
			veth102.0

ip a

2: lo: <LOOPBACK,UP,10000> mtu 16436 qdisc noqueue

link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00

inet 127.0.0.1/8 brd 127.255.255.255 scope host lo

4: eth0: <BROADCAST,MULTICAST,SLAVE,UP,10000> mtu 1500 qdisc pfifo_fast master bond0
qlen 1000

link/ether 00:15:60:ab:61:b4 brd ff:ff:ff:ff:ff:ff

6: eth1: <BROADCAST,MULTICAST,SLAVE,UP,10000> mtu 1500 qdisc pfifo_fast master bond0 qlen 1000
link/ether 00:15:60:ab:61:b4 brd ff:ff:ff:ff:ff:ff
8: bond0: <BROADCAST,MULTICAST,PROMISC,MASTER,UP,10000> mtu 1500 qdisc noqueue
link/ether 00:15:60:ab:61:b4 brd ff:ff:ff:ff:ff:ff
7: venet0: <BROADCAST,POINTOPOINT,NOARP,UP,10000> mtu 1500 qdisc noqueue
link/void
43: veth102.0: <BROADCAST,MULTICAST,UP,10000> mtu 1500 qdisc noqueue
link/ether 00:12:34:56:78:9b brd ff:ff:ff:ff:ff:ff
10: vlan5@bond0: <BROADCAST,MULTICAST,MASTER,UP,10000> mtu 1500 qdisc noqueue
link/ether 00:15:60:ab:61:b4 brd ff:ff:ff:ff:ff:ff
inet 192.168.5.4/24 brd 192.168.5.255 scope global vlan5
12: br5: <BROADCAST,MULTICAST,PROMISC,UP,10000> mtu 1500 qdisc noqueue
link/ether 00:12:34:56:78:9b brd ff:ff:ff:ff:ff:ff
14: vlan36@bond0: <BROADCAST,MULTICAST,MASTER,UP,10000> mtu 1500 qdisc noqueue
link/ether 00:15:60:ab:61:b4 brd ff:ff:ff:ff:ff:ff
inet 172.16.35.4/16 brd 172.16.255.255 scope global vlan36

http://forum.openvz.org/index.php?t=msg&goto=8854&&a mp;srch=vlan#msg_8854

<http://openvz.org/pipermail/users/2006-November/000399.html>

Subject: Re: bond+vlan
Posted by [sa10](#) on Thu, 12 Jul 2007 12:07:56 GMT
[View Forum Message](#) <> [Reply to Message](#)

Subject: Re: bond+vlan [SOLVED]
Posted by [sa10](#) on Thu, 12 Jul 2007 15:05:15 GMT
[View Forum Message](#) <> [Reply to Message](#)

sa10 wrote on Thu, 12 July 2007 15:07

```
VE0
eth0  eth1
 \  /
  bond0
 /  \

      \
      br0(bridge)
        \
        ve102.0 (veth)
          \
VE111      eth0 (ve102.0) 172.16.5.78
```

(
