Posted by Heartbeat on Wed, 05 Dec 2012 06:26:19 GMT
View Forum Message <> Reply to Message

/etc/init.d/net.bond0 start
 * Bringing up interface bond0
FATAL: Could not load /lib/modules/2.6.32-openvz-feoktistov.1/modules.dep: No such file or directory
 *   Cannot load the bonding module
 * ERROR: net.bond0 failed to start

(rev 01)

Toggle Spoiler

```
Module                  Size  Used by
simfs                   2570  6
vzethdev                6452  0
vznetdev                12841  12
vzrst                   125810  0
vzcpt                   104672  0
vzdquota                34474  6 [permanent]
vzmon                   14994  10 vzethdev,vznetdev,vzrst,vzcpt
vzdev                   1408  4 vzethdev,vznetdev,vzdquota,vzmon
pppoe                   8397  2
pppox                   1350  1 pppoe
ppp_deflate             3568  0
zlib_deflate            18074  1 ppp_deflate
ppp_synctty             4830  0
ppp_async               6083  0
ppp_generic             18959  9 pppoe,pppox,ppp_deflate,ppp_synctty,ppp_async
slhc                    4259  1 ppp_generic
tun                     11859  2
bonding                 76205  0
8139too                 15466  0
e100                    26537  0
e1000                   88763  0
```

Toggle Spoiler

KMEMSIZE="419430400:536870912"
LOCKEDPAGES="2048"
PRIVVMPAGES="65536:69632"
SHMPAGES="21504"
NUMPROC="240"
PHYSPAGES="0:unlimited"
VMGUARPAGES="33792:unlimited"
OOMGUARPAGES="26112:unlimited"
NUMTCPSOCK="360"
NUMFLOCK="188:206"
NUMPTY="16"
NUMSIGINFO="256"
TCPSNDBUF="1720320:2703360"
TCPRCVBUF="1720320:2703360"
OTHERSOCKBUF="1126080:2097152"
DGRAMRCVBUF="262144"
NUMOTHERSOCK="360"
NUMFILE="9312"
DCACHESIZE="3409920:3624960"
NUMIPTENT="128"
AVNUMPROC="180"
CPUUNITS="1000"
ORIGIN_SAMPLE="basic"
DISKSPACE="8G:10G"
DISKINODES="200000:220000"
QUOTATIME="0"
OSTEMPLATE="gentoo"
ONBOOT="yes"
NETDEV="eth3 eth4"
NETIF="ifname=br10,mac=00:18:51:B4:E4:9F,host_ifname=br10,host_mac=FE:FF:FF:FF:FF:FF;ifname=br11,mac=00:18:51:2B:64:0E,host_ifname=br11,host_mac=FE:FF:FF:FF:FF:FF;ifname=br12,mac=00:18:51:AF:83:7D,host_ifname=br12,host_mac=FE:FF:FF:FF:FF:FF"
HOSTNAME="bonding"
FEATURES="ppp:on "
DEVICES="c:108:0:rw "

cat /etc/vz/vz.conf
Toggle Spoiler

```
## Global parameters
VIRTUOZZO=yes
LOCKDIR=/vz/lock
DUMPDIR=/vz/dump
VE0CPUUNITS=1000

## Logging parameters
LOGGING=yes
LOGFILE=/var/log/vzctl.log
LOG_LEVEL=0
VERBOSE=0

## Disk quota parameters
DISK_QUOTA=yes
VZFASTBOOT=no

# Disable module loading. If set, vz initscript does not load any modules.
#MODULES_DISABLED=yes

# The name of the device whose IP address will be used as source IP for CT.
# By default automatically assigned.
#VE_ROUTE_SRC_DEV="eth0"

# Controls which interfaces to send ARP requests and modify APR tables on.
NEIGHBOUR_DEVS=detect

## Fail if there is another machine in the network with the same IP
ERROR_ON_ARPFAIL="no"

## Template parameters
TEMPLATE=/vz/template

## Defaults for containers
VE_ROOT=/vz/root/$VEID
VE_PRIVATE=/vz/private/$VEID
CONFIGFILE="basic"
DEF_OSTEMPLATE="centos-5"

## Load vzwdog module
VZWDOG="no"

## IPv4 iptables kernel modules to be enabled in CTs by default
IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle ipt_TCPMSS
ipt_tcpmss ipt_ttl ipt_length"
## IPv4 iptables kernel modules to be loaded by init.d/vz script
IPTABLES_MODULES="$IPTABLES"

## Enable IPv6
```

```
IPV6="yes"

## IPv6 ip6tables kernel modules
IP6TABLES="ip6_tables ip6table_filter ip6table_mangle ip6t_REJECT"


IPTABLES="iptable_filter iptable_mangle iptable_nat ipt_limit ipt_multiport ipt_tos ipt_TOS
ipt_REJECT ipt_TCPMSS ipt_tcpmss ipt_ttl ipt_LOG ipt_length ip_conntrack ip_conntrack_ftp
ip_conntrack_irc ipt_conntrack ipt_state ipt_helper iptable_nat ip_nat_ftp ip_nat_irc
ipt_REDIRECT"
```

Toggle Spoiler

```
config_eth3="null"
config_ppp0="ppp"
link_ppp0="eth3"
plugins_ppp0="pppoe"
username_ppp0="****"
password_ppp0="****"
pppd_ppp0="
        noauth
        defaultroute
        usepeerdns
        mru 1492
        mtu 1492
        persist
        noproxyarp
        lcp-echo-interval 10
        lcp-echo-failure 2
"
depend_ppp0() {
        need net.eth3
}

config_eth4="********* ***********"

modules="bonding"
config_bond0="null"
rc_need_bond0="net.ppp0 net.eth4"
mode_bond0="balance-alb"
miimon_bond="100"
slaves_bond0="ppp0 eth4"

routes_bond0="default"
```

Posted by lumen on Sat, 12 Jan 2013 08:51:12 GMT
View Forum Message <> Reply to Message

Posted by Heartbeat on Sun, 13 Jan 2013 23:16:07 GMT
View Forum Message <> Reply to Message