

---

Subject: Re: VPS doesn't work outside Node server  
Posted by [xwinner](#) on Sat, 10 Mar 2007 16:23:55 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Vasily Tarasov wrote on Wed, 07 March 2007 02:29 Thanks for information, you've posted.

1) This seems to be strange for me:

```
[root@scrameustache vz]# ip r l
192.168.0.101 dev veth101.0 scope link
192.168.0.101 dev venet0 scope link
192.168.0.0/24 dev eth0 proto kernel scope link src 192.168.0.10 metric 10
default via 192.168.0.1 dev eth0 metric 10
```

Please, remove routing via venet: you don't use this interface as far as I understand. Note, that this line will automatically appear if you did some time `vzctl set <veid> --ipadd` and config file of VE in question contents `IP_ADDRESS="..."`. So check that it doesn't happen.

2) Also, please, turn off iptables for a while, and check, does it solve the problem.

Thanks,  
Vasily

Thanks, i don't know how exactly remove venet route, is it only in the vps101.conf ?

this is my vps101.conf:

```
#
# it under the terms of the GNU General Public License as published by
#
# This program is distributed in the hope that it will be useful,
# MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
# GNU General Public License for more details.
#
# You should have received a copy of the GNU General Public License
# Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA
#
```

```
ONBOOT=yes
```

```
# Primary parameters
AVNUMPROC=40:40
NUMPROC=65:65
NUMTCPSOCK=80:80
NUMOTHERSOCK=80:80
VMGUARPAGES=6144:2147483647
# Secondary parameters
```

KMEMSIZE=2752512:2936012  
TCPSNDBUF=319488:524288  
TCPRCVBUF=319488:524288  
OTHERSOCKBUF=132096:336896  
DGRAMRCVBUF=132096:132096  
OOMGUARPAGES=6144:2147483647  
# Auxiliary parameters  
LOCKEDPAGES=32:32  
SHMPAGES=8192:8192  
PRIVVMPAGES=49152:53575  
NUMFILE=2048:2048  
NUMFLOCK=100:110  
NUMPTY=16:16  
NUMSIGINFO=256:256  
DCACHESIZE=1048576:1097728

PHYSPAGES=0:2147483647  
NUMIPTENT=128:128

DISKSPACE=4500000:4500000  
DISKINODES=200000:220000  
QUOTATIME=0

# CPU fair sheduler parameter  
CPUUNITS=1000  
VE\_ROOT=/vz/root/\$VEID  
VE\_PRIVATE=/vz/private/\$VEID  
OSTEMPLATE=mandriva-2006-i386-minimal  
ORIGIN\_SAMPLE=vps.basic  
#IP\_ADDRESS="192.168.0.101"  
HOSTNAME="vps101.localdomain."  
NAMESERVER="192.168.0.10"  
NETIF=ifname=eth0,mac=00:12:34:56:78:9A,host\_ifname=veth101.  
0,host\_mac=00:12:34:56:78:9B

---