Subject: Re: FC6 Precreated VE and ssh
Posted by jean1971 on Wed, 23 May 2007 13:53:55 GMT
View Forum Message <> Reply to Message

if it can be useful
on the same Hw I have FC5 and centos 5 that are working

exited from VE 101
[root@calvin ~]# cat /etc/ssh/ssh_config
$OpenBSD: ssh_config,v 1.21 2005/12/06 22:38:27 reyk Exp $

This is the ssh client system-wide configuration file. See
ssh_config(5) for more information. This file provides defaults for
users, and the values can be changed in per-user configuration files
or on the command line.

Configuration data is parsed as follows:
1. command line options
2. user-specific file
3. system-wide file
Any configuration value is only changed the first time it is set.
Thus, host-specific definitions should be at the beginning of the
configuration file, and defaults at the end.

Site-wide defaults for some commonly used options. For a comprehensive
list of available options, their meanings and defaults, please see the
ssh_config(5) man page.

Host *
ForwardAgent no
ForwardX11 no
RhostsRSAAuthentication no
RSAAuthentication yes
PasswordAuthentication yes
HostbasedAuthentication no
BatchMode no
CheckHostIP yes
AddressFamily any
ConnectTimeout 0
StrictHostKeyChecking ask
IdentityFile ~/.ssh/identity
IdentityFile ~/.ssh/id_rsa
IdentityFile ~/.ssh/id_dsa
Port 22
Protocol 2,1
Cipher 3des
Ciphers aes128-cbc,3des-cbc,blowfish-cbc,cast128-cbc,arcfour,aes192- cbc,aes256-cbc
EscapeChar ~

```
#   Tunnel no
#   TunnelDevice any:any
#   PermitLocalCommand no
Host *
      GSSAPIAuthentication yes
# If this option is set to yes then remote X11 clients will have full access
# to the original X11 display. As virtually no X11 client supports the untrusted
# mode correctly we set this to yes.
      ForwardX11Trusted yes
# Send locale-related environment variables
      SendEnv LANG LC_CTYPE LC_NUMERIC LC_TIME LC_COLLATE LC_MONETARY
LC_MESSAGES
      SendEnv LC_PAPER LC_NAME LC_ADDRESS LC_TELEPHONE LC_MEASUREMENT
      SendEnv LC_IDENTIFICATION LC_ALL
[root@calvin ~]#
```