

---

Subject: Re: openvz not working - Unable to open /dev/vzctl

Posted by [Rick C](#) on Mon, 20 Aug 2007 17:19:28 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

grub.conf looks like this

```
#boot=/dev/sda
default=0
timeout=5
splashimage=(hd0,0)/grub/splash.xpm.gz
hiddenmenu
title CentOS (2.6.18-8.1.8.el5)
    root (hd0,0)
    kernel /vmlinuz-2.6.18-8.1.8.el5 ro root=LABEL=/
    initrd /initrd-2.6.18-8.1.8.el5.img
title CentOS (2.6.18-8.1.8.el5.028stab039.1)
    root (hd0,0)
    kernel /vmlinuz-2.6.18-8.1.8.el5.028stab039.1 ro root=LABEL=/
    initrd /initrd-2.6.18-8.1.8.el5.028stab039.1.img
title CentOS (2.6.18-8.el5)
    root (hd0,0)
    kernel /vmlinuz-2.6.18-8.el5 ro root=LABEL=/
    initrd /initrd-2.6.18-8.el5.img
```

so needs to be

```
#boot=/dev/sda
default=0
timeout=5
splashimage=(hd0,0)/grub/splash.xpm.gz
hiddenmenu
#title CentOS (2.6.18-8.1.8.el5)
    root (hd0,0)
    kernel /vmlinuz-2.6.18-8.1.8.el5 ro root=LABEL=/
    initrd /initrd-2.6.18-8.1.8.el5.img
title CentOS (2.6.18-8.1.8.el5.028stab039.1)
    root (hd0,0)
    kernel /vmlinuz-2.6.18-8.1.8.el5.028stab039.1 ro root=LABEL=/
    initrd /initrd-2.6.18-8.1.8.el5.028stab039.1.img
#title CentOS (2.6.18-8.el5)
    root (hd0,0)
    kernel /vmlinuz-2.6.18-8.el5 ro root=LABEL=/
    initrd /initrd-2.6.18-8.el5.img
```

is that right? sorry am new to Vz

---