
Subject: help me please

Posted by [Mr.Ash](#) on Mon, 10 Sep 2007 10:30:59 GMT

[View Forum Message](#) <> [Reply to Message](#)

hello

i'm anew user using openvz i want know some thing

now i'm add ip " vzctl set 2 --ipadd 74.86.99.500 --setmode restart --save "

i want know how can i delete this ip

another question

```
# Sample configuration file for VPS based on OS template
```

```
#<agent>: redhat-9 with Plesk Server Administrator 7 application template
```

```
#
```

```
# Copyright (C) 2001-2005 by SWsoft. All rights reserved.
```

```
VERSION="2"
```

```
ONBOOT="yes"
```

```
CLASSID="2"
```

```
# UBC parameters (in form of barrier:limit)
```

```
# Primary parameters
```

```
AVNUMPROC="1440:1440"
```

```
NUMPROC="1920:1920"
```

```
NUMTCPSOCK="2880:2880"
```

```
NUMOTHERSOCK="2880:2880"
```

```
VMGUARPAGES="270336:2147483647"
```

```
# Secondary parameters
```

```
KMEMSIZE="88447385:91016396"
```

```
TCPSNDBUF="13762560:21626880"
```

```
TCPRCVBUF="13762560:21626880"
```

```
OTHERSOCKBUF="9008640:16777216"
```

```
DGRAMRCVBUF="2097152:2097152"
```

```
OOMGUARPAGES="208896:2147483647"
```

```
# Auxiliary parameters
```

```
LOCKEDPAGES="2048:2048"
```

```
SHMPAGES="172032:172032"
```

```
PRIVVMPAGES="524288:557056"
```

```
NUMFILE="8192:8192"
```

```
NUMFLOCK="1504:1648"
```

```
NUMPTY="128:128"
```

```
NUMSIGINFO="1024:1024"
```

```
DCACHESIZE="4192304:4317184"
```

```
PHYSPPAGES="0:2147483647"
```

```
NUMIPTENT="1024:1024"
```

```
IPTABLES="ipt_limit ipt_LOG ipt_multiport ipt_REJECT ipt_state ipt_TOS iptable_filter  
iptable_mangle "
```

```
NAMESERVER="208.67.222.222 208.67.220.220 10.0.80.11 10.0.80.12"
```

```
# Disk quota parameters (in form of softlimit:hardlimit)
```

```
DISKSPACE="10048576:11053434"
```

```
DISKINODES="2000000:2200000"
```

```
QUOTATIME="0"
```

```
QUOTAUGIDLIMIT="150"
```

```
# CPU fair sheduler parameter
```

```
CPUUNITS="1000"
```

```
OSTEMPLATE="centos-4"
```

```
TEMPLATES="devel-ce4"
```

```
OFFLINE_MANAGEMENT="yes"
```

and i'm set up cpanel

when i see in memory

	total	used	free	shared	buffers	cached
Mem:	2097152	400968	1696184	0	0	0
-/+ buffers/cache:		400968	1696184			
Swap:	0	0	0			
Total:	2097152	400968	1696184			

see swap is zero i have swap drive 12 gb in my server i want know how can i mount swap in vps

best regards

Alaa elden
