
Subject: Re: "vzctl stop" - hangs
Posted by [dagr](#) on Thu, 15 Nov 2007 08:22:03 GMT
[View Forum Message](#) <> [Reply to Message](#)

cause i need them to be read only

BTW - mount -n helps with error from mtab , but loop devices are still not detached

```
[dagr@ssw2-ca ~]$ date;sudo vzctl stop 1051206;date
Thu Nov 15 08:29:05 GMT 2007
Stopping VE ...
VE was stopped
umount
VE is unmounted
Thu Nov 15 08:31:06 GMT 2007
[dagr@ssw2-ca ~]$ ps -ef| grep loop
root  25193  1 0 08:28 ?      00:00:00 [loop0]
root  25200  1 0 08:28 ?      00:00:00 [loop1]
dagr  27545 24812 0 08:31 pts/3  00:00:00 grep loop
[dagr@ssw2-ca ~]$ sudo vzctl start 1051206
Starting VE ...
VE is mounted
Adding IP address(es): 10.5.1.206
Setting CPU units: 1000
Configure meminfo: 149152
Set hostname: vps-1051206.super.vz
VE start in progress...
[dagr@ssw2-ca ~]$ ps -ef| grep loop
root  25193  1 0 08:28 ?      00:00:00 [loop0]
root  25200  1 0 08:28 ?      00:00:00 [loop1]
root  27551  1 0 08:31 ?      00:00:00 [loop2]
root  27556  1 0 08:31 ?      00:00:00 [loop3]
dagr  29060 24812 0 08:31 pts/3  00:00:00 grep loop
[dagr@ssw2-ca ~]$ cat /etc/vz/conf/1051206.mount
#!/bin/bash
#echo mount
mount -n -o loop,ro /vz/shared_vps/php5_base/vps_static_loop_test /vz/root/$VEID/vps_static

mount -n -o loop,ro /vz/shared_vps/php5_base/vps_libs_loop /vz/root/$VEID/vps_libs
[dagr@ssw2-ca ~]$ cat /etc/vz/conf/1051206.umount
#!/bin/bash
echo umount
```

So eventually all 255 devices will be exhausted
