
Subject: Can't Enter VE

Posted by [scooter](#) on Fri, 07 Apr 2006 02:06:36 GMT

[View Forum Message](#) <> [Reply to Message](#)

Any ever had a problem when you try and do vzctl enter ID says enter failed?

I had a customer who it happened twice and says he did nothing out of the ordinary and i got it to happen to me today.

Restarting the VE doesn't help either.

I'll put my config below to see if that matters much.

I believe that should be 128 meg minimum and 256 meg burst.

Only thing i did was trying to check out this one mailserv setup program

<http://www.qmailtoaster.com/info/EZ-QmailToaster-MailServer.txt>

```
ONBOOT="yes"
```

```
# Primary parameters
```

```
NUMPROC="586:586"
```

```
AVNUMPROC="293:293"
```

```
NUMTCPSOCK="586:586"
```

```
NUMOTHERSOCK="586:586"
```

```
VMGUARPAGES="32768:2147483647"
```

```
# Secondary parameters
```

```
KMEMSIZE="24059084:26464992"
```

```
TCPSNDBUF="5619439:8019695"
```

```
TCPRCVBUF="5619439:8019695"
```

```
OTHERSOCKBUF="2809719:5209975"
```

```
DGRAMRCVBUF="2809719:2809719"
```

```
# Auxiliary parameters
```

```
LOCKEDPAGES="256:256"
```

```
SHMPAGES="117928:117928"
```

```
PHYSPAGES="0:2147483647"
```

```
NUMFILE="9376:9376"
```

```
NUMFLOCK="937:1030"
```

```
NUMPTY="58:58"
```

```
NUMSIGINFO="1024:1024"
```

```
DCACHESIZE="5243277:5400576"
```

```
NUMIPTENT="500:500"
```

```
DISKINODES="4704540:5174994"
```

QUOTATIME="0"
CPUUNITS="9256"
QUOTAUGIDLIMIT="40000"
OFFLINE_MANAGEMENT="yes"
NAMESERVER="ip's here"

DISKSPACE="5200000:5200000"

OOMGUARPAGES="2147483647:2147483647"
PRIVVMPAGES="128000:131072"

IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle ipt_TCPMSS
ipt_tcpmss ipt_ttl ipt_length"
