
Subject: *solved* cant login to virtual machine from other computers

Posted by [alex905](#) on Sun, 03 Feb 2008 17:56:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

i can log into my virtual machine from the host machine but not from remote computers. i can log into the host machine from remote computers though.

i added the ip 192.168.0.4 to the host machine at first (yes this is all on a private network) and then added the ip 192.168.0.5 to the virtual machine. a full restart later and no luck.

i then added the ip 192.168.0.5 as a second ip to the host machine by creating the file

```
ifcfg-eth0:1
```

the contents of the file are as follows

```
DEVICE=eth0
ONBOOT=yes
BOOTPROTO=static
IPADDR=192.168.0.5
NETMASK=255.255.255.0
GATEWAY=192.168.0.1
```

i noticed that the ifcfg-venet0 file on the host machine contains this code:

```
DEVICE=venet0
ONBOOT=yes
STARTMODE=onboot
```

is this normal or should this contain more information.

here is the output from the ifconfig command on the virtual machine.

```
lo      Link encap:Local Loopback
        inet addr:127.0.0.1  Mask:255.0.0.0
        UP LOOPBACK RUNNING  MTU:16436  Metric:1
        RX packets:4132306944 errors:0 dropped:0 overruns:0 frame:0
        TX packets:4096 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)

venet0  Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        -00
        inet addr:127.0.0.1  P-t-P:127.0.0.1  Bcast:0.0.0.0  Mask:255.255.255.
        255
        UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
        RX packets:102 errors:0 dropped:0 overruns:0 frame:0
        TX packets:71 errors:0 dropped:0 overruns:0 carrier:0
```

collisions:0 txqueuelen:0
RX bytes:8686 (8.4 KiB) TX bytes:8091 (7.9 KiB)

venet0:0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
-00
inet addr:192.168.0.6 P-t-P:192.168.0.6 Bcast:192.168.0.6 Mask:255.
255.255.255
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1

seems kins jumbled if you ask me. this is where i think the error is.

to add the ip i used the command

vzctl set 102 --ipadd 192.168.0.5 --save

any help is always greatly appreciated.