
Posted by [darkstar](#) on Thu, 07 Feb 2008 09:40:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
Building modules, stage 2.
MODPOST
WARNING: "round_jiffies_relative" [/media/disk1/drm/linux-core/drm.ko] undefined!
make[2]: *** [__modpost] Error 1
make[1]: *** [modules] Error 2
make[1]: Leaving directory `/media/disk1/2/linux-2.6.18'
make: *** [modules] Error 2
```

```
diff covz cvan
3,4c3,4
< # Linux kernel version: 2.6.18-028stab053
< # Thu Feb 7 10:51:20 2008
---
> # Linux kernel version: 2.6.18
> # Thu Feb 7 09:59:42 2008
39d38
< CONFIG_IPC_NS=y
45d43
< CONFIG_UTS_NS=y
53d50
< # CONFIG_TASK_IO_ACCOUNTING is not set
130,131d126
< CONFIG_SCHED_VCPU=y
< CONFIG_FAIRSCHEDE=y
157a153
> CONFIG_HOTPLUG_CPU=y
189a186
> CONFIG_SUSPEND_SMP=y
194a192,194
> CONFIG_ACPI_SLEEP=y
> CONFIG_ACPI_SLEEP_PROC_FS=y
> CONFIG_ACPI_SLEEP_PROC_SLEEP=y
202a203
> CONFIG_ACPI_HOTPLUG_CPU=y
```

```
1007d1007
< # CONFIG_BLK_DEV_DRBD is not set
1105c1105
< # SCSI Transport
---
> # SCSI Transport Attributes
1111,1112d1110
< CONFIG_SCSI_SAS_LIBSAS=m
< CONFIG_SCSI_SAS_LIBSAS_DEBUG=y
1136,1137d1133
< CONFIG_SCSI_AIC94XX=m
< CONFIG_AIC94XX_DEBUG=y
2748d2743
< # CONFIG_QUOTA_COMPAT is not set
2751,2754d2745
< CONFIG_SIM_FS=m
< CONFIG_VZ_QUOTA=m
< # CONFIG_VZ_QUOTA_UNLOAD is not set
< CONFIG_VZ_QUOTA_UGID=y
2959d2949
< # CONFIG_SYSRQ_DEBUG is not set
2961a2952
> # CONFIG_DETECT_SOFTLOCKUP is not set
2987,2999d2977
< # OpenVZ
< #
< CONFIG_VE=y
< CONFIG_VE_CALLS=m
< CONFIG_VZ_GENCALLS=y
< CONFIG_VE_NETDEV=m
< CONFIG_VE_ETHDEV=m
< CONFIG_VZ_DEV=m
< CONFIG_VE_IPTABLES=y
< CONFIG_VZ_WDOG=m
< CONFIG_VZ_CHECKPOINT=m
<
< #
3002,3006d2979
<
< #
< # Grsecurity
< #
< # CONFIG_GRKERNSEC is not set
3008a2982,2988
> CONFIG_SECURITY=y
> CONFIG_SECURITY_NETWORK=y
> # CONFIG_SECURITY_NETWORK_XFRM is not set
> CONFIG_SECURITY_CAPABILITIES=m
```

```
> CONFIG_SECURITY_ROOTPLUG=m
> # CONFIG_SECURITY_SECLVL is not set
> # CONFIG_SECURITY_SELINUX is not set
3060,3070d3039
<
< #
< # User resources
< #
< CONFIG_USER_RESOURCE=y
< CONFIG_USER_RSS_ACCOUNTING=y
< CONFIG_UBC_IO_ACCT=y
< CONFIG_USER_SWAP_ACCOUNTING=y
< CONFIG_USER_RESOURCE_PROC=y
< # CONFIG_UBC_DEBUG is not set
< CONFIG_UBC_IO_PRIO=y
```
