
Subject: Re: vzctl set changes configuration on the fly?

Posted by [pva0xd](#) on Wed, 02 Apr 2008 08:13:25 GMT

[View Forum Message](#) <> [Reply to Message](#)

Location of config file is different, but here it is:

```
vz ~ # cat /etc/vz/conf/101.conf
# Copyright (C) 2000-2007 SWsoft. All rights reserved.
#
# This program is free software; you can redistribute it and/or modify
# it under the terms of the GNU General Public License as published by
# the Free Software Foundation; either version 2 of the License, or
# (at your option) any later version.
#
# This program is distributed in the hope that it will be useful,
# but WITHOUT ANY WARRANTY; without even the implied warranty of
# MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
# GNU General Public License for more details.
#
# You should have received a copy of the GNU General Public License
# along with this program; if not, write to the Free Software
# Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA
#
```

```
VERSION="2"
```

```
ONBOOT="yes"
```

```
# UBC parameters (in form of barrier:limit)
# Primary parameters
AVNUMPROC="40:40"
NUMPROC="65:65"
NUMTCPSOCK="80:80"
NUMOTHERSOCK="80:80"
VMGUARPAGES="25600:28160"
# Secondary parameters
KMEMSIZE="10485760:12582912"
TCPSNDBUF="319488:524288"
TCPRCVBUF="319488:524288"
OTHERSOCKBUF="132096:336896"
DGRAMRCVBUF="132096:132096"
OOMGUARPAGES="133120:9223372036854775807"
# Auxiliary parameters
LOCKEDPAGES="32:32"
SHMPAGES="8192:8192"
PRIVVMPAGES="76800:81920"
NUMFILE="2048:2048"
```

NUMFLOCK="100:110"
NUMPTY="16:16"
NUMSIGINFO="256:256"
DCACHESIZE="1048576:1097728"

PHYSPAGES="0:9223372036854775807"
NUMIPTENT="128:128"

Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="4097152:4306868"
DISKINODES="400000:420000"
QUOTATIME="0"

CPU fair sheduler parameter
CPUUNITS="100000"
OFFLINE_MANAGEMENT="yes"
HOSTNAME="cacti.rcline.ru"
IP_ADDRESS="172.16.0.41"
CPULIMIT="90"
