
Subject: Re: bug in vzctl 3.0.23-1pve3

Posted by [fdef](#) on Mon, 07 Dec 2009 11:25:56 GMT

[View Forum Message](#) <> [Reply to Message](#)

Ok thx for your explanation.

But, do you see any errors in my vps scripts?

```
root@test:/etc/vz/conf# cat vps.*
#!/bin/bash
source /etc/vz/vz.conf
source ${VE_CONFFILE}
mount --bind /home ${VE_ROOT}/home
mount --bind /vz/backups ${VE_ROOT}/backups
#!/bin/bash
source /etc/vz/vz.conf
source ${VE_CONFFILE}
umount ${VE_ROOT}/home
umount ${VE_ROOT}/backups
```

Cause i don't understand.

Nothings is mounted..

```
root@test:/etc/vz/conf# mount | grep 102
```

I start 102 contener, and nothings will be mount even vps.umount script start before vps.mount.
And i'm not really shure, vps.mount script start.

```
root@test:/etc/vz/conf# vzctl start 102
Starting container ...
umount: /var/lib/vz/root/102/home: not mounted
umount: /var/lib/vz/root/102/backups: not mounted
Error executing umount script /etc/vz/conf/vps.umount
Setting CPU units: 1000
Setting CPUs: 1
Configure meminfo: 262144
Set hostname: test
File resolv.conf was modified
Setting quota ugidlimit: 0
Configure veth devices: veth102.0
Adding interface veth102.0 to bridge vmbr1 on CT0 for CT102
Container start in progress...
```

```
root@test:/etc/vz/conf# mount | grep 102
```

Do you think, if vps.umount exit with error status, the vps.mount script didn't start ?

```
root@test:/etc/vz/conf# vzctl stop 102
Stopping container ...
Container was stopped
umount: /home: not mounted
umount: /home: not mounted
umount: /var/lib/vz/backups: not mounted
umount: /var/lib/vz/backups: not mounted
Error executing umount script /etc/vz/conf/vps.umount
```

Thx fdef
