
Subject: Re: i very need help i have some problem
Posted by [Nabil taha](#) on Wed, 13 Jan 2010 16:54:40 GMT
[View Forum Message](#) <> [Reply to Message](#)

that : OpenVZ Configuration

```
#####  
##          ##  
##  vePortal Generated OpenVZ  ##  
##    Configuration File      ##  
##          ##  
#####  
#  
# =====  
# Global Parameters  
# =====  
#  
VIRTUOZZO=yes  
LOCKDIR=/vz/lock  
DUMPDIR=/vz/dump  
VE0CPUUNITS=1000  
#  
# =====  
# Logging Parameters  
# =====  
#  
LOGGING=yes  
LOGFILE=/var/log/vzctl.log  
LOG_LEVEL=0  
VERBOSE=0  
#  
# =====  
# Disk Quota Parameters  
# =====  
#  
DISK_QUOTA=yes  
VZFASTBOOT=no  
#  
# =====  
# Disable Module Loading  
# if set, vz initscript will not load any modules  
# =====  
#  
#MODULES_DISABLED=yes  
#  
# The name of the device whose IP address will be used as source IP for CT.  
# By default automatically assigned.  
#VE_ROUTE_SRC_DEV="eth0"
```

```
#
# Controls which interfaces to send ARP requests and modify APR tables on.
NEIGHBOUR_DEVS=detect
#
# =====
# Template Parameters
# =====
#
TEMPLATE=/vz/template
#
# =====
# Container Default Parameters
# =====
#
VE_ROOT=/vz/root/$VEID
VE_PRIVATE=/vz/private/$VEID
CONFIGFILE="veportal"
DEF_OSTEMPLATE="centos-5-x86"
#
## Load vzwdog module
VZWDOG="no"
#
## IPv4 iptables kernel modules
IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle ipt_TCPMSS
ipt_tcpmss ipt_ttl ipt_length"
#
## Enable IPv6
IPV6="no"
#
## IPv6 ip6tables kernel modules
IP6TABLES="ip6_tables ip6table_filter ip6table_mangle ip6t_REJECT"
```

and i use panel : Veportal

thanks for help
